




Configure your dial-up connection using pppconfig

Set Up An Internet Connection

To set up your LAN-based Internet connection, right-click on the desktop and go to **System > Net Setup > netcardconfig**. Use this utility to enter your IP address, DNS address, etc.


If you have a dial-up connection, use the **Net Setup > Dial-up PPP** utility and set up your connection.

You can now use any of the three browsers to surf the Net—Dillo, Firefox or Netrik, accessible from the **Apps > Net > Browsers** menu.

Use Apt To Install Packages

DSL is based on the Debian kernel, so you can use the **apt-get** command to install new programs and updates from the Web. First, you need to enable Apt. Right-click on the desktop and go to **Apps > Tools > Enable Apt**.

If you know the package name for the software you want to download, type **sudo apt-get install <package>** in a terminal window, and the application will be downloaded and installed from Debian's repositories on the Internet.



Configure your LAN connection with netcardconfig

Other Boot Labels

You can also use these boot labels while DSL boots. (You don't need to use the preceding "dsl" for these.)

Expert	Interactive startup/setup
FailSafe	(Almost) no hardware detection
install	Menu-based install system for easy access to all possible installs
lowram	Low RAM usage GUI with Minimal Desktop

DSL Cheat Codes

They're not really ways to *cheat*, but with these options, you can get some more control over the way DSL behaves. At the boot prompt, type **dsl** followed by the cheat code to get the effect you want.

Code	Effect
2	Runlevel 2, Textmode only
base	Skip myDSL and only load the base system
desktop=	Choose your window manager. Options: fluxbox, jwm
dma	Turn on DMA acceleration for all drives
host=web123	Set hostname
lang={us/cs/da/de/es/fr/nl/it/pl/ru/sk...}	Choose Language/Keyboard
mem=xxM	Specify the RAM in MB. If you are running on a machine with very low RAM, use this code to tell DSL how much memory is available. For example: for a machine with 24 MB of RAM to use, use "mem=24M" ("mem" must be lowercase and the "M" at the end must be uppercase)
minimal	DSL will use the "Minimal" fluxbox theme
mydsl={hda1/sda1}	Where to store your myDSL apps
nodhcp	Skip network setup
noicons	Use a plain desktop
no{scsi/pcmcia/usb/agp/swap/apm/apic/mce/ddc}	Disable detection for the specified hardware
protect	On boot, DSL will prompt you for an encryption password and then triple des encrypt the backup file
restore	Load previously saved configuration
restore={hda1/sda1/floppy}	Specify saved configuration location
secure	On boot, DSL will prompt for passwords for root and dsl
{ssh/lpd/nfs/syslog/monkey/ftp}	Start these daemons at boot. (A <i>daemon</i> is a program that runs in the background and provides a service)
tohd=/dev/hda1	Copy CD to HD partition and run
vga=normal	Most compatible video mode
xsetup	Prompts you to setup X

Shoot to Kill

If you've used Linux before, you will know that the **[Ctrl] + [Alt] + [Esc]** combination is manna when you need to kill an errant application with a single click. You can get this in DSL as well.

Start Ted by double-clicking the icon on the desktop. Navigate to the **.fluxbox** folder and open the file called "keys". You will get an error saying "keys" is not in the rich text format—ignore the error.

When Ted opens with "keys", add this entry at the end:

Control Mod1 Escape :ExecCommand xkill

Restart the Fluxbox window manager by right-clicking on the desktop and going to **Window Manager > Restart**. Now, when you need to kill an application, you can use **[Ctrl] + [Alt] + [Esc]** and then click on the misbehaving app to end it. ■



The Ted Text Editor