



net Settings\Zones\0
HKEY_USERS\S-1-5-20\Software\
Microsoft\Windows\CurrentVersionInter
net Settings\Zones\0
and so on (all of the entries in the HKEY_USERS
branch that do not contain the word “Classes”).

Vanishing Space

After using the Automatic Update to install all the necessary updates for Windows XP, I found that the free space on my system drive has been reduced significantly. I remember that this cannot be accounted by the size of the automatic updates alone, because I see that more than twice that amount of space has been gobbled up.

Harish Chaturvedi

Windows downloads all the updates to a temporary folder and then installs them. However, it does not delete them after installation—that is why you find that a lot of your free space has been lost. Open Windows Explorer and go to the folder C:\WINDOWS\Software Distribution. Delete the folder called Download. This will free up most of the space that had been occupied. In Windows Explorer, go to Tools > Folder Options and select the View tab. Ensure that Show hidden files and folders is selected. Open the Windows folder. Locate the \$NtUninstall... folders. Note the name or KB number that follows Uninstall. Delete the folder. Start the Registry Editor. Expand SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall. Delete the subkey with the name noted above. Expand SOFTWARE\Microsoft\Windows\CurrentVersion\App Management\APCach. Delete the subkey with the name noted above.

Prints Gone Wrong

When I try to print a page of a Web site from Internet Explorer, the text/image at the right margin is cut off.

Ashish Sharma

This problem is caused due to a bug in Internet Explorer, which is not able to determine the width of the printable area of the page. The better way to get rid of this problem is by installing of Internet Explorer 7, which does not have this bug. If you are unable to do so for some reason, you can print the page in another browser such as Mozilla or Opera. You can also try to use this workaround: Open Internet Explorer, open the web page you wish to print and go to File > Page Setup. Set the left and right margins to 0 and click on OK. Try printing the page again. If this does not resolve the problem, then click on File > Page Setup and change the Orientation setting to landscape.

Dynamic Disk

I have a SATA 120GB drive. It has a primary and an extended partition. The extended partition has 4 logical partitions. I added a 320GB SATA drive and created partitions in it. The new disk shows up as a dynamic disk. What is a dynamic drive? I was creating an image of my Ubuntu partition on one of these

volumes and Acronis showed a warning saying the drive was dynamic.

Kenshin on Thinkdigit Forum

Dynamic disk is a type of initialisation that is done by Windows. Dynamic disks provide advanced features and volume management as compared to basic disks. The Dynamic Disk must have been initialized when you created partitions for the drive formatted them. Converting a Basic disk to Dynamic is possible without losing any data using Disk Management feature in Computer Management. Click on Start > Control Panel > Administrative Tools > Computer Management. To convert a Dynamic disk back to Basic, you will need to remove all the volumes on the disk which means you need to back up all you data on these partitions. Right-click on the disk you want to convert and click Convert to Basic Disk.

Dead Links

I have been facing a weird problem—hyperlinks that are in my e-mails in Outlook Express do not open when I click on them.

Arshpreet Kaur

Make sure that you have a default Web browser configured. To make Internet Explorer the default browser, open Internet Explorer and go to Tools > Internet Options. Click on the Programs tab. Ensure that Internet Explorer should check to see if it is the default browser checked. Close Internet Explorer and reopen it. When you see the message “Internet Explorer is not currently your default browser. Do you wish to make it the default?”, select Yes.

Disable any third party pop-up blocking software that may be running on your computer.

You may also need to repair the file association for hyperlinks in the following way. Open Windows Explorer go to Tools > Folder Options. Click on the File Types tab and locate the entry named URL:HyperText Transfer Protocol. Click on Advanced.

Select open and click Edit in the Edit File Type dialog box. Make sure that the field Application to perform this action contains: C:\Program Files\Internet Explorer\iexplore.exe -nohome (if your default browser is Microsoft Internet Explorer) or C:\PROGRA~1\MOZILL~1\FIREFOX.EXE -url "%1" (if your default browser is Mozilla Firefox.) Please note: These paths may need to be modified if IE or Firefox are not installed in the default locations. Also keep in mind that the 8-character short path needs to be used for Firefox. The Use DDE box must be checked and the DDE Message: must be: “%1”,-1,0,,,,, (or “%1”,,0,0,,, for Firefox.). Also ensure that Application: is set to: IExplore (for Microsoft Internet Explorer) or: Firefox (for Mozilla Firefox.) Ensure that DDE Application Not Running: is blank. Ensure that Topic: is WWW_OpenURL.



HOW TO

Create Your First Quake III Map


... it's not as hard as you'd think!

Rossi Fernandes

Quake III Arena is one of the best multiplayer games ever, and easily one of the most refined game engines ever made. To make your very first map in Quake III, you need a copy of the game (naturally) and GTKRadiant—which is freely available for download at www.qeradiant.com. GTKRadiant is used to create maps for many games other than Quake III, so most of these techniques will be helpful in other games like Doom 3, Quake 4 and so on.

Configuring GTKRadiant

When you start GTKRadiant for the first time, you're asked to point out to the location of your Quake III folder. By default, it points out to C:\Program Files\Quake III Arena. Make sure you change the path to your installed path, and remember to specify the game as Quake III Arena. When GTKRadiant loads, you will notice that the interface seems rather complicated. To make things a little simpler, we will change the layout of the viewports to 4 views by going to Edit > Preferences > Interface > Layout. Restart GTKRadiant and there will be three views showing the map through the X,Y and Z axis and the fourth one showing a real-time




Changing GTKRadiant's default viewport layout is preferable—it makes things


preview. To use the preview, right click in the window and use the directional arrow keys to move around like you would in the game.

Creating Brushes

Brushes are the building blocks that make up the structures. The walls, the floor, the pillars are created with brushes. To create a brush, simply drag a sufficiently large box in one of the three views. In this example, we'll make a box and then make it hollow—like an empty room, but without windows. To make the box hollow, click on the Make Hollow button in the toolbar. The rotate, scale and move tools can be found on the tool-



Every surface you create can be given its own texture



Textures need to be moved into place and aligned using the Surface Inspector

bar above. While making the structure, you need to keep in mind that there are to be no leaks—no empty spaces leading outside the map. If required, make an additional hollow enclosure outside the main structure.

Adding Textures

A map can't have one single texture painted all over—we now need to set texture for each of these surfaces. Hold the [Shift] key down and left click on a surface. Now, click on the Texture Browser button, or hit [T]. Click on a category of texture from the left and click on the texture on the right to apply the texture on the surface. Depending on the size of the texture and the object, the proportions will be messed up. To fix this, start the Surface Inspector—View > Surface Inspector or [S]. Here you can select the surface in the same manner and change the alignment and tiling for the texture.

Adding Gameplay Elements

Things like weapon ammo, armor, jump pads and weapons contribute

to a fun-filled map. A spawn point is the bare essential—to add one, right click on the view where you want it added and select Info > info_player_deathmatch. You'll need many more depending on the number of players you plan on having in your map or you'll have all the players spawning at that single spot. Similarly, place weapons, armor and ammunition. Lights are absolutely necessary unless you plan on playing hide-and-seek in the dark. Right-click in the top view and select Light. You can give it an intensity and colour here.

Test Run

To compile, first save the map to (File > Save). Then, click on the Build menu and select one of the compile presets. Compiling the map can take a while if it's very detailed and has many lights in it. If your compile fails, there's a good chance that there are leaks in the map—GTKRadiant will tell you where they are.

To test the map, copy the compiled .bsp file from the location where it was compiled to

your Quake III Arena\baseq3\maps folder. Start Quake III. Make sure the pure server is turned off by typing /sv_pure 0. Type /map mapname or /devmap mapname and your map should load.

Packing Up

When you feel you are satisfied with the results, its time to pack your map up so you can send it over to your friends so fragging can commence. Create an empty folder called Maps and copy the .bsp file into it. Next, use a compression tool such as WinRAR or WinZip and create a ZIP archive out of the maps folder. Rename the .zip file to .pk3. Now you can give your friends the .PK3 file to be dumped into the BASEQ3 folder of their installation.

If you are the one hosting the server, then you can have Quake III automatically send the map from your machine. Just make sure the clients use the command /cl_AllowDownload 1 and you use the command /sv_AllowDownload 1. ■

rossi.fernandes@thinkdigit.com