

Comments: This behaviour may occur after you upgrade to Windows XP.

Cause: This may occur if the network card in your computer is not enabled.

Solution: To resolve this issue, enable the network card, and then run the Network Setup Wizard: in the Control Panel, click Performance and Maintenance, and then click System. In the System Properties dialog box, click the Hardware tab, and then click Device Manager. In Device Manager, click Network adapters. On the Action menu, click Enable. Quit Device Manager. Now, in the Control Panel, click Network and Internet Connections, and then click Network Connections. In Network Connections, click Network Setup Wizard under Network Tasks, and then follow the on-screen steps. Finally, restart your computer.

► **Problem:** Internet Explorer does not automatically connect to the Internet.

Solution: Visit <http://support.microsoft.com/default.aspx?scid=kb;EN-US;Q231643>

► **Problem:** The computer keeps disconnecting from the Internet.

Cause: This could be due to Internet Explorer or Outlook Express settings.

Solution: In Internet Explorer, do to Tools > Internet Options > Connections > Dial-up Settings > Advanced Dial-up settings. Make sure that 'Disconnect when connection may no longer be required' is turned off, and that the option to disconnect if idle is turned off as well.

Outlook Express options can cause problems as well. Go to Outlook Express > Tools > Options > Connections, and make sure "Connect to this account using" is not selected for each mail and news account. Make sure there is no conflict in account settings—each account should show the connection option "Any available". Next, go to Tools > Options > Connections and turn off "Hang up after send/receive".