

board. On the next screen you will see three lines related to the boot entry of Linux. Choose the line stating '*kernel..*' and hit *[E]* again. A new editable screen appears, and at the end of the line type '*single*' and hit *[Enter]*. This will take you back to the previous screen. Now, press *[B]* key of your keyboard to boot the OS in Single User Mode.

9.1.3 Changing Boot Loaders

A user is allowed the freedom to change the boot loader as required. Some basic Linux OS come with a default boot loader and an alternative one need to be downloaded from the Internet. For instance, if you have a boot loader LILO and the installation did not feature Grub then you will have to download it from the internet and install it too. Thereafter you need to make that switch between the two boot loader.

LILO to Grub

Download and install Grub from <http://www.gnu.org/software/grub/>

To switch the boot loader issue the following command
#grub-install /dev/hda [Enter]

Grub to LILO

If LILO is not installed in your system then search on the internet for a package relevant to your distribution or refer this site:
<http://www.linuxloader.com/>

If you have a distribution that uses anaconda as its installer, then most likely you will have a file in */etc* named '*lilo.conf.anaconda*' copy this file to */etc/lilo.conf* and then execute the lilo command.

```
#cp /etc/lilo.conf.anaconda /etc/lilo.conf + [Enter]  
#lilo -v + [Enter]  
#lilo -t + [Enter]
```