

Navigate to:

HLM\System\CurrentControlSet\Services\Dmadmin\Parameters

Create a new DWORD value here called EnableDynamicConversionFor1394 if it doesn't exist, or if it does, modify the existing value. 0 is the default value; set it to 1 to enable the conversion to a dynamic disk. You may need to restart or log out for the change to take effect.

Do not convert FireWire disk drives to dynamic disk drives if they will be moved to other hosts.

Juggle The Keys Around

How often do you use the Windows key that's found on almost all keyboards today? Probably not too often, except when a program setup takes up the entire screen and you need to access your icons. If you press it accidentally, you need to press [Esc], which is a minor irritant. There's a registry hack to disable the Windows key should you wish to do so.

Navigate to:

HLM\System\CurrentControlSet\Control\Keyboard Layout

Here, create a new Binary value (or modify the existing value) called "Scancode Map" and set it to the following. Don't bother with what appears in the editing box—just type in the value below exactly as it is (you don't need to use the spacebar):

```
00 00 00 00 00 00 00 00 03 00 00 00 00 00 5B E0 00 00 5C E0 00
00 00 00
```

Logging out and logging back in should bring the change into effect, but you might need to restart.

In fact, you can change any key to any other! Essentially, each key has a code, and you need to specify how many keys you are