

`/Default`

Allows you to change the Default boot entry.

`/EMS`

Allows you to configure the `/redirect` switch for headless support for a boot entry.

`/Debug`

Allows you to specify the port and baud rate for remote debugging for a specified boot entry.

`/Addsw`

Allows you to add predefined switches for a specific boot entry.

`/Rmsw`

Allows you to remove predefined switches for a specific boot entry.

`/Dbg1394`

Allows you to configure 1394 port debugging for a specified boot entry.

Chkdsk

Creates and displays a status report for the disk. Also lists and corrects errors on the disk. Used without parameters, `chkdsk` displays the status of the disk in the current drive.

Syntax:

```
chkdsk [ drive:] [ /p] [ /r]
```

drive: Specifies the drive that you want `chkdsk` to check.

/p: Performs an exhaustive check even if the drive is not marked for `chkdsk` to run. This parameter does not make any changes to the drive.

/r: Locates bad sectors and recovers readable information. Implies `/p`.