

/i: Specifies that the search is not case-sensitive.

"string": Required. Specifies the group of characters that you want to search for. You must enclose string in quotation marks (that is, "string").

[Drive :][Path] FileName: Specifies the location and name of the file in which to search for the specified string.

Ftp

Transfers files to and from a computer running a File Transfer Protocol (FTP) server service such as Internet Information Services. Ftp can be used interactively or in batch mode by processing ASCII text files.

Syntax:

```
ftp [-v] [-d] [-i] [-n] [-g] [-s:FileName] [-a] [-w:WindowSize] [-A] [Host]
```

-v: Suppresses the display of FTP server responses.

-d: Enables debugging, displaying all commands passed between the FTP client and FTP server.

-i: Disables interactive prompting during multiple file transfers.

-n: Suppresses the ability to log on automatically when the initial connection is made.

-g: Disables file name globbing. Glob permits the use of the asterisk (*) and question mark (?) as wildcard characters in local file and path names.

-s: FileName: Specifies a text file that contains ftp commands. These commands run automatically after ftp starts. This parameter allows no spaces. Use this parameter instead of redirection (<).

-a: Specifies that any local interface can be used when binding the FTP data connection.

-w: WindowSize: Specifies the size of the transfer buffer. The default window size is 4096 bytes.

-A: Logs onto the FTP server as anonymous.

Host: Specifies the computer name, IP address, or IPv6 address of the FTP server to which to connect. The host name or address, if specified, must be the last parameter on the line.