

attribute, right-click (and hold it) the select lock selected, hide selected, or lock and hide selected.

Channel Box Quick Notes

You can select a bone's attribute in the channel box, then in the display view, middle-click and hold the mouse, then move the mouse left and right to change the attributes. Set Driven Key is a great tool to adjust multiple bones without selecting every one of them. This tool is great for fingers/fists, tails, and other things like that.

To create a new attribute, select Add Attribute from the Modify menu. It will open a window where you will give it a name (in Long Name); make the attribute key able, displayable, or hidden; select its data type (vector: a bunch of numbers; integer: whole numbers like 1, 5, 10; string: name; float: all numbers like 1.5, -56, 85.021; boolean and enum which you will probably never use); and set its numeric attribute properties minimum, maximum, and default value. Clicking OK will add the attribute to whichever bone/object you currently have selected.

To access Set driven Key, go to **Animate > Set Driven Key Set**. This opens a box. The driver is an object, which when adjusted, moves the driven. What you will do is load up the bone that is controlling all of the movement into the driver, and then load the bone that is going to be moved into the driven. Select the first bone and click on **load driver**. This will make the bone names appear in the left box of the driver section. Then, select the attribute that is going to be controlling all of the movements from the right box of the driver section. Now select one of the bones that are going to be controlled by the attribute and select load driven. This should make the bone names appear in the left box of the driven section.

Now you are going to set the default, minimum, and maximum values of how the driven bones is going to be adjusted. Select the bone in the driver section, along with its value to control adjustment of the driven bone, set its adjusting value in the channel box to the default value and press key. Now set its adjusting value to the maximum, select the Driven bone and move it into the position in which you would want it at the maximum value, and press key. Now select the Driver bone again, set its adjusting value to the minimum value, select the Driven bone and move it into the position in which you would want it at the minimum value, and press key. Now, when you adjust the Driver bone's adjusting value, you should see the Driven bone move accordingly.