

service instance. Each service instance is named with Fault Management Resource Identifier (FMRI). The FMRI includes the service name and the instance name. For example, the FMRI for the sendmail service is `svc:/network/smtp:sendmail`, where `network/smtp` identifies the service and `sendmail` identifies the service instance. Examples of other acceptable FMRI include:

- `svc://localhost/system/system-log:default`
- `svc:/system/system-log:default`
- `system/system-log:default`

Services can be enabled from the GNOME Desktop or by using the command line.

Quick Tip

Adobe Flash Player plugin for Firefox is available at <https://pkg.sun.com/extra> repository. Check out a screencast on how to install flash player in OpenSolaris at <http://thinkdigit.com/opensolaris>

3.6.1 Enabling services from the desktop

You can enable and disable some services that are installed on an OpenSolaris system by using the Services application that is located in the GNOME desktop. Enabling and disabling services by using the Services application is equivalent to using the `svcadm` command. The services that can be viewed and managed from the desktop depend on the authorisations that are assigned to the user account and the service itself.

3.6.2 How to enable services from the desktop

Step 1: Choose **System > Administration > Services**.

The Services window is displayed. Services that are enabled have a check mark in the check box next to the service. If the service is disabled, the check box is blank.

Step 2: To enable a service, place a check mark next to the service, then save the changes. Services are disabled in the same way.

Digit Subscription

Subscribe to the Digit developer newsletter at www.thinkdigit.com/newsletter

3.6.3 Enabling services from the command line

The `svcs` command is used to identify which services are installed on a system. The `svcadm` command is used to administer or change the state of a service. To configure SMF services, you must assume a role with appropriate privileges, such as the root or Primary Administrator role.

For example, if you have to check if Network Automagic (nwam) service is currently running or disabled, then open a terminal and execute: