

graphical desktop.

1. On the system to be installed, insert the Live CD, then boot the system.
2. At the console login, type the default login and password. The default user login and password for OpenSolaris is **jack**.
3. Assume the root role by using the **su** command and password. The password is **opensolaris**.

```
$ su root
```

Password: **opensolaris**

4. Enable the service for the ssh remote login program.

```
# svcadm enable ssh
```

5. Display the IP address that is assigned by DHCP to the target system.

```
# ifconfig -a
```

6. On the remote system, open a terminal window, then type:

```
$ ssh -X ip-address-of-target -l jack
```

where **ip-address-of-target** is the output of the

ifconfig -a command that you ran on the target system. Running this command on the remote system opens a secure shell, enabling you to access the target system to use the GUI installer.

7. Assume the root role.

```
$ su root
```

Password: **opensolaris**

8. Run the GUI installer:

```
# /bin/gui-install
```

9. After the installation completes, reboot the target system.

If you are unable to log in to your installed system, use the following procedure.

Quick Tip

After switching from the graphical boot to a text boot, there is no way to switch back to the graphical boot screen. Wait for the graphical login screen to appear. If there is anything wrong, the text boot screen will show warning message and the graphical login screen will not appear.

{dev.works}

Don't forget to visit the definitive resource for programmers from Digit: dev. Works at devworks.thinkdigit.com

3.7.2 How to troubleshoot your OpenSolaris login

Troubleshooting login issues requires you to gain access to the system by booting in single-user mode, so you can troubleshoot the nature of problem and apply the appropriate solution. This procedure includes the steps for booting a system in single-user mode, as well as solutions to the most common login problems.