

```

users/home/neil          18K    16.5G          18K    /
users/home/neil
users/home/neil@yest      0          -          18K    -
# zfs rename -r users/home@yest @2daysago
# zfs list -r users/home
NAME                                USED    AVAIL    REFER
MOUNTPOINT
users/home                        76K    16.5G
22K    /users/home
users/home@2daysago            0          -          22K    -
users/home/markm              18K    16.5G
18K    /users/home/markm
users/home/markm@
2daysago                      0          -          18K    -
users/home/marks              18K    16.5G
18K    /users/home/marks
users/home/marks@
2daysago                      0          -          18K    -
users/home/neil               18K    16.5G
18K    /users/home/neil
users/home/neil@
2daysago                      0          -          18K    -

```

4.9.4 Displaying and accessing ZFS snapshots

You can enable or disable the display of snapshot listings in the `zfs list` output by using the `listsnapshots` pool property. This property is enabled by default. If you disable this property, you can use the `zfs list -t snapshot` command to display snapshot information. Or, enable the `listsnapshots` pool property. For example:

```

# zpool get listsnapshots tank
NAME      PROPERTY      VALUE      SOURCE
tank      listsnapshots on      default
# zpool set listsnapshots=off tank
# zpool get listsnapshots tank
NAME      PROPERTY      VALUE      SOURCE
tank      listsnapshots off
local

```

Snapshots of file systems are accessible in the `.zfs/snapshot` directory