

- SSHFS : `sshfs#user@server:/share`

5.2 Mount point

A mount point is a location on your directory tree to mount the partition. The default location is `/media` although you may use alternate locations such as `/mnt` or your home directory.

You may use any name you wish for the mount point, but you must create the mount point before you mount the partition.

For example : `/media/windows`

`sudo mkdir /media/windows`

5.3 File System Type

You may either use `auto` or specify a file system. `Auto` will attempt to automatically detect the file system of the target file system and in general works well. In general `auto` is used for removable devices and a specific file system or network protocol for network shares.

Examples:

- `auto`
- `vfat` - used for FAT partitions.
- `ntfs`, `ntfs-3g` - used for ntfs partitions.
- `ext2`, `ext3`, `jfs`, `reiserfs`, etc.
- `udf`, `iso9660` - for CD/DVD.
- `swap`.

5.4 Options

Options are dependent on the file system.

You may use "defaults" here and some typical options may include :

- `defaults` = `rw`, `suid`, `dev`, `exec`, `auto`, `nouser`, and `async`.
- `/home` = The options for a separate home partition should be `nodev`, `nosuid`
- `ntfs/vfat` = permissions are set at the time of mounting the partition with `umask`, `dmask`, and `fmask` and cannot be changed with commands such as `chown` or `chmod`.

We advise `dmask=027`, `fmask=137` (if you use `umask=000` all your files will be executable). More permissive options would be `dmask=000`, `fmask=111`.

For mounting samba shares you can specify a username and password, or better a credentials file. The credentials file contains should be owned by `root.root` with permissions = `0400` .

5.5 Common options

- `sync/async` - All I/O to the file system should be done (a)synchronously.
- `auto` - The filesystem can be mounted automatically (at bootup, or when