

```
<activity
    android:name=".AutoResponder"
    android:label="Auto Responder Setup"/>
</application>


<uses-permission    android:name="android.permission.ACCESS_
GPS"/>
<uses-permission
    android:name="android.permission.ACCESS_LOCATION"/>
<uses-permission    android:name="android.permission.RECEIVE_
SMS"/>
<uses-permission android:name="android.permission.SEND_SMS"/>
</manifest>
```

To enable the auto-responder, return to the Emergency Responder Activity and update the startAutoResponder method stub that you created in the previous example. It should open the AutoResponder Activity you just created.

```
private void startAutoResponder() {
    startActivityForResult(new Intent(EmergencyResponder.this,
                                     AutoResponder.class), 0);
}
```

10. If you start your project, you should now be able to bring up the Auto Responder Setup window to set the auto-response settings.
11. The final step is to update the requestReceived method in the Emergency Responder Activity to check if the auto-responder has been enabled. If it has, the requestReceived method should automatically execute the respond method, using the message and location settings defined in the application's Shared Preferences.

```
public void requestReceived(String
_from) {
    if (!requesters.contains(_from)) {
        lock.lock();
        requesters.add(_from);
```



Autoresponder