

Get a list of the current network configurations using `getConfiguredNetworks`. The list of `WifiConfiguration` objects returned includes the network ID, SSID and other details for each configuration.

To use a particular network configuration, use the `enableNetwork` method, passing in the network ID to use and specifying `true` for the `disableAllOthers` parameter:

```
// Get a list of available configurations
        List<WifiConfiguration> configurations = wifi.
getConfiguredNetworks();
    // Get the network ID for the first one.
    if (configurations.size() > 0) {
        int netID = configurations.get(0).networkId;
        // Enable that network.
boolean disableAllOthers = true;
wifi.enableNetwork(netID, disableAllOthers>true);
    }
```

8.5 Automating the configuration

To connect to a Wi-Fi network, you need to create and register a configuration. Normally, your users would do this using the native Wi-Fi configuration settings, but there's no reason you can't expose the same functionality within your own applications, or for that matter replace the native Wi-Fi configuration Activity entirely.

Network configurations are stored as `WifiConfiguration` objects. The following is a non-exhaustive list of some of the public fields available for each Wi-Fi configuration:

- **BSSID:** The BSSID for an access point
- **SSID:** The SSID for a particular network
- **networkId:** A unique identifier used to identify this network configuration on the current device
- **priority:** The network configuration's priority to use when ordering the list of potential access points to connect to
- **status:** The current status of this network connection, which will be one of the following: `WifiConfiguration.Status.ENABLED`, `WifiConfiguration.Status.DISABLED` or `WifiConfiguration.Status.CURRENT`

The configuration object also contains the supported authentication techniques, as well as the keys used previously to authenticate with this access point. 