




Figure 4: The default virtual networking interface



Figure 5: Select a virtualisation method

guest OS, then you need to select the second option and from the drop down window, select the option that says 'NAT to any physical device'. The following window gives you a summary of the virtual network. Simply, click *Finish* here. There... *now* does your screen look like Figure 4?

However, this sort of a NAT-based set-up is invisible from systems on your LAN. In fact, forget LAN, you can't even access the guest system from within the host system by means of tools like *ssh* or *ping*. So what is to be done now? This is where the bridged network comes into the picture. To set it, you first need to edit the `/etc/sysconfig/network-scripts/ifcfg-eth0` file as the root user. By default, it should look somewhat like the following

```
# nVidia Corporation MCP67 Ethernet
```



Figure 6: How to connect to the host network?




Figure 7: Allocate memory and CPU

```
DEVICE=eth0
HWADDR=00:1d:60:66:aa:3b
ONBOOT=yes
BOOTPROTO=dhcp
USERCTL=yes
IPV6INIT=no
NM_CONTROLLED=no
TYPE=Ethernet
PEERDNS=yes
```

In here, you have to make the following changes:

- comment out the `BOOTPROTO` line
- Add a new line: `BRIDGE=switch`

Here's what mine looks like after the editing work:

```
# nVidia Corporation MCP67 Ethernet
```