




Figure 5: Druid console




Figure 6: Druid: Load data




Figure 7: Druid querying

## Druid installation

Druid may be installed on a laptop for experimental purposes. It has various startup configurations. You should try the micro-quickstart configuration for evaluating Druid. The nano-quickstart configuration requires very few

resources — one CPU and 4GB RAM.

The basic requirements for installing Druid on your computer are as follows:

- Operating systems like Linux and Mac OS X. Similar UNIX based OSes are also supported. The official documentation lists that

Windows is not supported.

- Java 8 (update 92 or later).
- If your system satisfies the above requirements, download version 0.21.1 from <https://www.apache.org/dyn/closer.cgi?path=/druid/0.21.1/apache-druid-0.21.1-bin.tar.gz>. Then extract it from the terminal and navigate to the directory:

```
tar -xzf apache-druid-0.21.1-bin.tar.gz
cd apache-druid-0.21.1
```

Druid can be started with the micro-quickstart configuration using the following command:

```
./bin/start-micro-quickstart
```

This command launches instances of ZooKeeper and Druid services:

```
$ ./bin/start-micro-quickstart
Running command[zookeeper], logging to[/
apache-druid-0.21.1/var/sv/zk.log]:
bin/run-zk conf
Running command[coordinator-overlord],
logging to[/apache-druid-0.21.1/var/
sv/coordinator-overlord.log]: bin/run-
druid coordinator-overlord conf/druid/
single-server/micro-quickstart
Running command[broker], logging to[/
apache-druid-0.21.1/var/sv/broker.log]:
bin/run-druid broker conf/druid/single-
server/micro-quickstart
Running command[router], logging to[/
apache-druid-0.21.1/var/sv/router.log]:
bin/run-druid router conf/druid/single-
server/micro-quickstart
Running command[historical], logging
to[/apache-druid-0.21.1/var/sv/
historical.log]: bin/run-druid
historical conf/druid/single-server/
micro-quickstart
Running command[middleManager],
logging to[/apache-druid-0.21.1/var/
sv/middleManager.log]: bin/run-druid
middleManager conf/druid/single-server/
micro-quickstart
```

Once the services are started, the Druid console can be opened by