

```
p proxmox-ve-2.6.24
The Proxmox Virtual Environment
p proxmox-ve-2.6.32
The Proxmox Virtual Environment
p proxmox-ve-2.6.35
The Proxmox Virtual Environment
p proxmox-virtual-environment
```

You should install proxmox-ve-2.6.32, because Proxmox developers consider this version to be stable and have included it in Proxmox 1.6:

```
# aptitude install proxmox-ve-2.6.32
Reading package lists... Done
...
Need to get 67.4MB of archives. After unpacking 79.7MB will be
used.
Do you want to continue? [Y/n/?]
```

Restart the system and voilà! Proxmox is installed. Easy, isn't it?

Upgrading Proxmox to a newer version is as simple as running 'aptitude update' and 'aptitude safe-upgrade', and rebooting your box. It couldn't be easier.

As you can see, initial Proxmox deployment consists of simple and clear steps. Let's proceed to the next step—virtual environment configuration and customisation, where we'll create virtual network devices and storage pools.

Configuration

You'll need a Web browser like Mozilla Firefox or Google Chrome to log in to the Proxmox control centre. A Java Runtime Environment and browser plug-ins are essential for video and keyboard access through VNC to an OS inside a virtual container. Later, I'll also show you how to configure a VNC channel, and use just a standalone vncviewer. Point the browser to a newly deployed Proxmox host, and after authorisation (the host's local root user credentials) you'll see the main console page. The home page (Figure 4) displays the overall system load, the amount of free memory and swap space. Before you create a VM, you must configure network interfaces for it, as well as pre-configure storage space for the VMs. Jump into the 'Configuration > System > Interface Configuration' section. This tab displays all network devices configured on the host. Click the red arrow near 'Interface configuration'. Choose what network device you need, 'bridge' or 'bond', and name it (e.g., vmbr5). Bonding devices can operate in different modes: 'balance-rr', 'active-backup', 'balance-xor', 'broadcast', '802.3ad', 'balance-tlb' or 'balance-alb'. They also bring interesting functionality to the VM—particularly, to double the bandwidth to a new VM, create a bonded network device and choose '802.3ad' mode, and then assign it to a VM.




Figure 3: Only 10 minutes required to install Proxmox




Figure 4: The management console home page



Figure 5: Create a virtual Ethernet device for virtual container

The next task is to create storage to hold OpenVZ machines. Just for the record, it can store QEMU containers' files too.

You're free to create LVM volumes either manually, or from within the Proxmox management console: 'Configuration > Storage > Storage List > Add LVM Group'. For OpenVZ storage space, though, you must do it manually. Create a physical volume as follows:

```
# pvcreate -v /dev/cciss/c0d0p3
```

Now create a VolumeGroup named VG: