

- Enter inventory name and if you want to create this inventory for a specific organisation, you can select the created organisation, or else choose *Default* and then save it.
- In variable, we pass those parameters that we want to apply to all hosts connected to that inventory. Here we want to connect with hosts/target machines using ssh. So we have to pass *ansible_connection: ssh* in variable.
- If you get an error related to the Python interpreter while executing the template, add *ansible_python_interpreter: '{{ ansible_playbook_python }}'* in variables of that inventory, as shown in Figure 7.




Figure 5: Dashboard

Configuration of hosts

- To add a host, which you want to access using AWX, click on *Hosts* and then select the *Add* button. Add the IP address or host name of the host/target machine, choose the inventory to which you want to add this host, and then add details of that host and save it as shown in Figure 8. We have to pass variables in hosts, as shown below:

```
ansible_host: 172.16.145.49           # ip address
of host
ansible_user: suchi                   #
enter username of host you are accessing
ansible_become: true                  #
Ansible_become used for privilege escalation.
ansible_ssh_pass: Suchi@123           # password of
ansible_user of host machine
ansible_sudo_pass: Suchi@123
```

If the *ansible_user* is root, then we don't need to pass *ansible_sudo_pass*. If you want to connect with the target machine/hosts through ssh without password, it is not required to pass *ansible_ssh_pass* variables in the host configuration.

Adding credentials

- If you want to access the target machine/hosts using the password, we can directly select *demo credentials* and nothing needs to be configured.




Figure 6: Screenshot to add organisation