




Figure 7: Screenshot to add inventory




Figure 8: Screenshot to add hosts

- But if you want to access the target machine/hosts using ssh without password, we have to use the ssh key sharing mechanism.
- Go inside minikube where AWX is installed by using the command:

```
docker exec -it minikube_container_id /bin/bash
```

- Generate the public and private keys of minikube machine using the command:

```
ssh-keygen
```

- Now, copy the public key of minikube in all target

machines/hosts using the command `ssh-copy-id user@ip` from the minikube terminal. It will copy the public key of minikube in targets.

- Here, *user* is the user of the host you are accessing and its IP that you have mentioned in this host configuration.
- Now, you have to add the private key of minikube in the AWX credential. This private key is available in `cat ~/.ssh/id_rsa`.

Next, go to the credential tab in AWX, click on the **Add** button, give credential name, and copy paste the private key.

In user name, add the login user of AWX who will execute templates. In our case, we are using *admin*. Select the name of the organisation with which the credential is associated.