

the screen to save the settings and enable the service.

- The next sub-category is 'Domains'. This will list all the local domains. Click on the button under 'Domain IP addresses' and remove your public IP from this using the 'Delete' button under 'Action'. Click the 'Save changes' button on the top left of the screen to save the settings and enable the service.
- Click on the back button of your browser and click on the button under 'Hostname'. Then click on the button under 'IP address' and delete your public IP from here too. This removal will prevent your public IPs from serving DNS requests from the Web. Click 'Save changes' at the top left of the screen to save the settings and enable the service.

DHCP set-up

The DNS has almost been setup. We will now set up the DHCP server. Follow the steps below:

- Click DHCP under 'Infrastructure'.
- Uncheck 'Enabled' to stop DHCP requests on the external interface. Click 'Save changes' at the top left of the screen to save the settings and enable the service.
- Click 'Configuration' of *eth1* to set up DHCP.
- Click 'Custom IP address' and add 172.22.22.1 for the default gateway.
- For the search domain, select 'Zentyal domain'.
- For the primary nameserver, select 'Custom' and add 8.8.8.8.
- For the secondary nameserver, add 8.8.4.4.
- For NTP server, set 'Local Zentyal NTP'.
- Click the 'Change' button to temporarily save changes.
- Under DHCP ranges, you can see the interface IP address set as 172.22.22.1, the subnet as 172.22.22.0/24 and the available range as 172.22.22.1 – 172.22.22.254. To provide the IP address to clients, you need to set up the DHCP range. Click the 'Add new' button under 'Ranges'. Under 'Name' enter 'lan'; under 'From' enter 172.22.22.2, and under 'To' enter 172.22.22.254. Click 'Add', and then click the 'Save changes' button at the top left of the screen to save the settings.
- Then click 'Dynamic DNS options'.
- Select 'Enabled' under the 'Dynamic DNS options' and click the 'Change' button. Click the 'Save changes' button at the top left of the screen to save the settings.
- In the end, click on 'Modules status' under 'Core'.
- Select DHCP and click on the 'Save changes' button at the top left of the screen to save the settings and enable the service.

Captive portal set-up

With these settings, clients will get IP addresses automatically. The next part involves setting up the captive portal. As discussed earlier, it is used to limit access to the network. Follow the steps below:

- Click 'Captive portal' under 'Gateway'.
- Select 'Limit Bandwidth usage'.
- Define the bandwidth quota. Enter the size in MBs.
- Select the period for that quota—from Day, Week and

Month. Hit 'Change' to save.

- Click 'Checkbox enabled' under captive interfaces and then click the 'Save changes' button at the top left of the screen to save settings and enable the service.

With all the steps mentioned earlier, you will be able to configure and set up DNS, DHCP and captive portal on your server.

Test the configuration

To test the configuration on a client, which could be Windows or Linux, remove any IPs from the interface of the client. Connect it to the network. Wait for a few seconds. Your client will receive an IP address from the server. To check the IP address received on the client, type the following command:

```
ipconfig /all
```

...on your Windows clients.

And for Linux clients, type...

```
$ ifconfig eth0
```

Things you might miss

Here's a list of some of the commonly missed settings during set-up. If you missed them, you can configure them from the dashboard.

- If you missed the IP set-up, then follow the steps below:
 - Click 'Network' under 'Core', then click 'Interfaces'.
 - You can now set the external interface (eth0) from here. You can also set the internal interface (eth1).
 - Click 'Save Changes'.
- If you missed the gateway, follow the steps below:
 - Click on 'Network' under 'Core', then click 'Gateway'.
 - Click 'Add new'.
 - Provide the name to the gateway.
 - Provide the IP address of the gateway.
 - Select 'Default checkbox'.
 - Click 'Save Changes'.
- If you missed some of the components from the installation, follow the steps below:
 - Click 'Software Management' under 'Core'.
 - Click 'Zentyal components'.
 - Then select any component that you have missed during installation.
 - In the end, click 'Install' to install the component.

In my next tutorial I will discuss the HTTP proxy, traffic shaping, firewalls and users, and computers. 

By: Gaurav Parashar

The author is a FOSS enthusiast, and loves to work with open source technologies like Moodle and Ubuntu. He works as assistant dean (for IT students) at Inmantec Institutions, Ghaziabad, UP. He can be reached at gauravparashar24@gmail.com