

that you designate the VPS for sending and receiving mail.

Set up the MX entries for *pop*, *imap* and *smtp* to point to your IP address. Create an *mx* record that points to a CNAME record which, in turn, points to an A record that points to the mail server IP.

Most registrars will have a Web interface that allows you to do this. The interface may differ slightly but the DNS records are specified in a standard format.

Setting up Postfix

Open the Postfix *main.cf* configuration file and make the following changes:

```
nano /etc/postfix/main.cf
```

Comment the following lines:

```
#inet_interfaces = localhost
#mydestination = $myhostname, localhost.$mydomain, localhost
```

Now add these lines at the bottom of the file. Use your host and domain names. The IP addresses indicate the IPs that are allowed to connect to Postfix. At the very least, these addresses should contain 127.0.0.0/8, which indicates localhost. The other addresses mentioned are that of our server's IPs; you should substitute these with the addresses of your servers if you want the mail host to serve more than one application for sending out emails.

```
myhostname = mail.sastratechologies.in
mydomain = sastratechologies.in
myorigin = $mydomain
home_mailbox = mail/
mynetworks = 127.0.0.0/8 146.185.133.41 146.185.129.131
188.226.155.27
inet_interfaces = all
mydestination = $myhostname, localhost.$mydomain, localhost,
$mydomain
smtpd_sasl_auth_enable = yes
smtpd_sasl_type = cyrus
smtpd_sasl_security_options = noanonymous
broken_sasl_auth_clients = yes
smtpd_sasl_authenticated_header = yes
smtpd_recipient_restrictions = permit_sasl_
authenticated,permit_mynetworks,reject_unauth_destination
smtpd_tls_auth_only = no
smtp_use_tls = yes
smtpd_use_tls = yes
smtp_tls_note_starttls_offer = yes
smtpd_tls_key_file = /etc/postfix/ssl/smtpd.key
smtpd_tls_cert_file = /etc/postfix/ssl/smtpd.crt
smtpd_tls_CAfile = /etc/postfix/ssl/cacert.pem
smtpd_tls_received_header = yes
```

```
smtpd_tls_session_cache_timeout = 3600s
tls_random_source = dev:/dev/urandom
```

Now open the master configuration file and enter the following lines:

```
nano /etc/postfix/master.cf
smtps inet n - n - - smtpd
-o smtpd_sasl_auth_enable=yes
-o smtpd_tls_security_level=encrypt
-o smtpd_recipient_restrictions=permit_sasl_
authenticated,reject
-o smtpd_client_restrictions=permit_sasl_authenticated,reject
-o broken_sasl_auth_clients=yes
```

Ensure that you retain the two blank spaces before the '-o' when you save the file. Postfix is a bit finicky when it reads this file and will report vague errors if this space convention is not adhered to. Now let's restart Postfix and *sasl auth* services:

```
service postfix start
service saslauthd start
chkconfig --level 235 postfix on
chkconfig --level 235 saslauthd on
```

Check SMTP connectivity

Let us now check if Postfix is running by Telnet. From your terminal, run the following command:

```
telnet localhost 25
```

...then type:

```
ehlo localhost
```

Your transcript will look something like what follows:

```
[root@sastratechologies.in sridhar]# telnet localhost 25
Trying ::1...
Connected to localhost.
Escape character is '^['.
220 mail.sastratechologies.in ESMTP Postfix
ehlo localhost
250-mail.sastratechologies.in
250-PIPELINING
250-SIZE 10240000
250-VRFY
250-ETRN
250-ENHANCEDSTATUSCODES
250-8BITMIME
250-DSN
quit
221 2.0.0 Bye
```