

Figure 1: First installation screen




Figure 2: HDD formatting warning



Figure 3: Set-up complete

Following these steps completes the basic installation. The network diagram should resemble Diagram 2. Figures 1 to 7 show the various steps of the installation.

Once the installation is complete, the IPCop firewall starts functioning immediately between the Green and Red networks, blocking all incoming requests from Red to Green. To configure and fine-tune the firewall, use the friendly Web interface via https://GREEN_IP:445 (connect to the Green interface IP). IPCop can also be accessed via SSH, but the IPCop service runs on the custom TCP port 222.

Client TCP/IP configuration

Only two TCP/IP settings are required on client PCs, so



Figure 4: Configure networking




Figure 5: Network configuration menu




Figure 6: Network configuration type

set the default gateway and DNS server to the IPCop Green IP address.

IPCop proxy configuration

The IPCop proxy uses the TCP port 800 to accept, process, log and forward requests from the Green (Internal) network to Red (Internet), and sends received replies back to the originating internal system. There are two ways to configure the IPCop proxy from web based GUI:

- Transparent mode:** This diverts all traffic received from the Green network on port 80 to the IPCop proxy port. No changes are required in client browser settings. To enable a transparent proxy, go to *Services - Proxy* and select the *Transparent on Green* check-box.