



Figure 1: Status screen



Figure 2: System screen

on the Openfiler 2.3 Installation ISO image (for x86/64). The hardware used here is a simple PC with an Intel 2.8 GHz dual-core CPU, with 1 GB of RAM and an 80 GB SATA hard disk.

Caution: For a fresh set-up, the target hard disk for installation will be wiped “clean” by the installer. Ensure any desired data is backed up!

Start the installation by booting from a CD prepared from the downloaded ISO image. Openfiler supports a text- as well as GUI-based installation; continue with the latter. There are practically no surprises during this installation process. The most important steps during installation are hard-disk partitioning and networking, which are explained here.

Disk partitioning

If you have two hard disks installed in the computer, select the first hard disk for installation. Partition the hard disk manually, if you have a single hard disk.

Table 2: Disk partitions

Partition	Mount Point	Minimum Size	Recommended Size	File System	Purpose
Boot	/boot	100 MB	256 MB	ext3	Kernel and other files needed for booting.
Root	/	1024 MB	2048 MB	ext3	OS installation
Swap	N. A.	1024 MB	2048 MB	N.A.	Swap space



Figure 3: Network access configuration



Figure 4: Volume group management



Note: If you choose auto partitioning, all the disk space is taken for the Openfiler distro, leaving no space for data.

Create three partitions, as detailed below. Tick the ‘*Force to be a primary partition*’ check-box while creating all the three partitions shown in Table 2.

Network configuration

Ensure you enter correct values for host-name, default gateway and DNS servers. These settings are important for patching Openfiler. Though Openfiler can get an IP address from a DHCP server, use the Edit tab at the top right corner to specify a static IP address and subnet mask. Don’t forget to tick the ‘*Activate on boot*’ check-box.

Continue through the rest of the installation, and reboot to complete the first phase of installation. The Openfiler box can now be accessed in these ways:

1. Use the username ‘root’ and the password configured during the installation process for access at the Openfiler PC console, or via SSH from another system.
2. Access the Web administration interface by navigating to <https://ipaddress:446> (the IP address of the Openfiler PC) from any node. Here, the default login name is *openfiler*, and the password is *password*.

Updates

Immediately after the first reboot, patch the new installation. Log in at the console, and run the command *conary updateall*. The