



Figure 5: New volume creation



Figure 6: LDAP server




Figure 7: Canary update

time required for updates depends on your Internet connection speed. Repeat the same command till you get a 'Nothing to be updated' message. Now the installation is at the stage where



Figure 8: Add new user

you can create volumes, shares, groups and users, and start using the Openfiler box. Log in to the Web administration interface. The first screen you see is status (Figure 1), where hardware and important system information is displayed.

Initial set-up

Proceed to the System tab (Figure 2), which has the options to (re-)configure Openfiler system parameters like network configuration; clock set-up (define a Network Time Protocol (NTP) server address and time zone); UPS set-up (Openfiler, if connected to an intelligent UPS, can be configured to shut-down when the UPS signals low battery state); backup/restore configuration; and secure console (SSH access).



Note: Some advanced options, such as bonded interface creation and HA cluster set-up are not covered here.

Complete the 'Network Access Configuration'.

You can allow access to a single host, or the full subnet. Under our test set-up, we allowed access to the 192.168.51.0/255.255.255.0 subnet (Figure 3).

The next step is to create a volume group on the desired hard disk, using the 'Volumes' tab (Figure 4). Under the test set-up, the group name was *firstvolume*. Continue by selecting *firstvolume* from the *Add Volumes* tab. The new volume should be defined along with disk-space allocation and volume type (ext3/XFS or iSCSI). Here, we defined *Songs* as the volume name (Figure 5), allotting 37000 MB of disk space. We preferred ext3, from the data-recovery perspective. The time required to complete this step will vary depending on CPU and hard disk speed.



Note: You may use the *Managing Volumes* tab to increase the size of a created volume (from the corresponding *Volume Edit* link), and create snapshots of the volumes. Note that once a snapshot is created for a volume, the allotted disk space cannot be increased.