

```
/home/user/linux/folder1/work/office
```

This is equivalent to making use of the variable '\$OLDPWD', which stores information related to your previous working directory.

Type the following command:

```
echo $OLDPWD
```

...to display your previous working directory.

—Satish, satish.ashwath@gmail.com

Configure Yum behind the HTTP proxy

 Under normal conditions, Yum won't work if you are using the Internet behind the proxy. On several occasions, exporting the 'http_proxy' variable will also not work. In this case, you need to set the 'http proxy' by editing the configuration file of Yum (/etc/yum.conf).

To configure Yum to use a proxy server is really simple. You can open the 'yum.conf' file in a text editor and add the following code:

```
# The proxy server or IP address:port number
proxy=http://proxy.server.com:8080
```

Type the following command if you are using user name and password for your proxy settings:

```
# The proxy account for yum connections
proxy_username=userid
proxy_password=password
```

—Aman Agarwal, neshuagarwal1909@gmail.com

Use your mobile phone to connect to the Internet

 You need to perform the following steps as the root user; after connecting your mobile phone with the USB cable, type the commands listed below. Here I have used my Nokia mobile phone to connect to the Internet.

Step 1:

```
# lsusb
Bus 003 Device 006: ID 0421:006b Nokia Mobile Phones
Bus 003 Device 001: ID 0000:0000
Bus 002 Device 001: ID 0000:0000
Bus 004 Device 001: ID 0000:0000
Bus 005 Device 001: ID 0000:0000
Bus 001 Device 001: ID 0000:0000
```

You can get the vendor ID and product ID from the output of the above command. For example, my Nokia mobile phone's vendor ID is 0421 and product ID is 006b.

Step 2:

```
#/sbin/modprobe usbserial vendor=0x(vid) product=0x(pid)
```

Here, replace 'vid' and 'pid' with the IDs generated as output from the previous command.

Step 3:

```
#wvdialconf create
```

Step 4:

Now configure 'wvdial' by adding the following parameters:

```
#vi /etc/wvdial.conf
[Dialer Defaults]
Modem = /dev/ttyACM0
Baud = 460800
Init1 = ATZ
Init2 = ATQ0 V1 E1 S0=0 &C1 &D2 &FCLASS=0
INIT5 = AT+CGDCONT=1,"IP","airtelgprs.com"
ISDN = 0
Modem Type = Analog Modem
Phone = *99#
Username =username
Password =password
Stupid Mode = 1
```

These settings are for my service provider. You can try similar settings for your service provider.

Step 5:

Add the following in the 'resolv.conf'

```
#vi /etc/resolv.conf
nameserver 202.56.238.5
nameserver 202.56.240.5
```

Step 6:

After you have finished configuring the above, just run:

```
#wvdial
```

This will connect you to the Internet, provided you have an active GPRS connection on your mobile.

—Vilas Bale, vilas.bale@gmail.com

END 

Share Your Linux Recipes!

The joy of using Linux is in finding ways to get around problems—take them head on, defeat them! We invite you to share your tips and tricks with us for publication in LFY so that they can reach a wider audience. Your tips could be related to administration, programming, troubleshooting or general tweaking. Submit them at www.linuxforu.com. The sender of each published tip will get an LFY T-shirt.