

Figure 1: Startup screen of Clonezilla



Figure 2: Mount Clonezilla image directory

However, the steps mentioned here are very general and can be used to take a back-up of and restore of any system on a local disk, SSH, NFS or Samba server.

The steps to set up the NFS server

We need to first set up the NFS server to back up and restore our partition/disks. On your Ubuntu server, install *nfs-kernel-server* by issuing the following command:

```
:~$  sudo-apt-get install nfs-kernel-server
```

There are three configuration files that relate to an NFSv4 server: */etc/default/nfs-kernel-server, /etc/default/nfs-common and /etc/exports*.

These config files, in our example, would look like what's shown below.

In */etc/default/nfs-kernel-server*, I have set:

```
NEED_SVCGSSD = no # no is default
```

… because I am not activating NFSv4 security this time.

In */etc/default/nfs-common* I set:



Figure 3: Mode selection



Figure 4: Network selection

Figure 5: IP address of NFS server

```
NEED_IDMAPD = yes
NEED_GSSD = no # no is default
```

… because I want the UID/GUID to be mapped from names.

In order that the ID names get automatically mapped, you should modify the */etc/idmapd.conf* file with the following lines in the Mapping section:

```
[Mapping]

Nobody-User = nobody
Nobody-Group = nogroup
```

We need NFS to share files on the network at one common place.

Create a folder backup in */mnt/*

```
:~$  sudo mkdir /mnt/backup
:~$  sudo chmod 777 /mnt/backup
```

Inform the network about this folder. Edit the file */etc/exports* using the commands mentioned below:

```
:~$  sudo su
:~$  echo "/mnt/backup       *(rw,sync,no_root_squash) " >> /
etc/exports
```

This completes the set-up of the NFS server on an Ubuntu machine.

Backing up a Windows partition

In this section, I will demonstrate how to back-up a Windows partition using Clonezilla. Boot Clonezilla using a CD/DVD