

Table 1: DeltaCloud - Compute driver functionality for popular cloud service providers

	Create new instances	Start stopped instances	Stop running instances	Reboot running instances	Destroy instances	List all/get details about hardware profiles	List all/get details about realms	List all/get details about images
Amazon EC2	yes	no	yes	yes	yes	yes	yes	yes
Eucalyptus	yes	no	yes	yes	yes	yes	yes	yes
IBM SmartCloud	yes	yes	yes	yes	yes	yes	yes	yes
GoGrid	yes	no	yes	yes	yes	yes	yes	yes
Rackspace	yes	no	yes	yes	yes	yes	yes	yes
Terremark	yes	yes	yes	yes	yes	yes	yes	yes
vSphere	yes	yes	yes	yes	yes	yes	yes	yes
OpenStack Store (swift)	yes	yes	yes	yes	yes	yes	yes	yes

Table 2: Deltacloud - Storage driver functionality for popular cloud service providers

	Create new buckets	Update/delete buckets	Create new blobs	Update/delete blobs	Read/write blob attributes	Read/write individual blob attributes
Amazon S3	yes	yes	yes	yes	yes	yes
Eucalyptus Walrus	yes	yes	yes	yes	yes	yes
Rackspace CloudFiles	yes	yes	yes	yes	yes	yes
Microsoft Azure	yes	yes	yes	yes	yes	yes
Google Storage	yes	yes	yes	yes	yes	yes
Openstack object-store (swift)	yes	yes	yes	yes	yes	yes

Table 3: DeltaCloud - Cloud provider credentials for popular cloud service providers

Cloud	Driver	Username	Password
Amazon EC2/S3	ec2	Access Key ID	Secret Access Key
Eucalyptus	eucalyptus	Access Key ID	Secret Access Key
GoGrid	gogrid	API Key	Shared Secret
IBM SmartCloud	sbc	Username	Password
Microsoft Azure (Storage Account only)	azure	Public Storage Account Name	Primary Access Key
OpenStack	openstack	OpenStack user	The username is OpenStack user name and tenant_name concatenated with a '+' and password is your openstack service password.
Rackspace	rackspace	Rackspace user name	API Key
Terremark	terremark	Username	Password
VMware vSphere	vsphere	vSphere user	vSphere user password

Parameters:

By default, the server binds to the local host (127.0.0.1).

If the objective is to bind to the DeltaCloud server from a different computer:

```
SYNTAX --> C:\Users\Mitesh>deltacloud -i ec2 -r 192.168.1.23 -p 9988
OUTPUT --> Starting DeltaCloud API :: ec2 :: http://192.168.1.23:9988/api
DL is deprecated, please use Fiddle
>> Thin web server (v1.5.0 codename Knife)
>> Debugging ON
>> Maximum connections set to 1024
>> Listening on 192.168.1.23:9988, CTRL+C to stop
```

To use the browser interface,

- Open your browser, i.e., Mozilla, Chrome, IE
- Go to the URL `http://<hostname>:<port>/api`
 - <hostname> is the host name or IP address
 - <port> is the port supplied on the command line

Deltacloud with Amazon Web Services

You can use a Web interface as described in the above section to view instances available in the cloud environment. To access the Web interface, the user needs to provide access credentials based on the driver used. This authentication is HTTP basic authentication, where one needs to provide the username and password.

For the Amazon public cloud, the access key ID is your username and the secret key is your password. Each drive