


```
test-VirtualBox*CLI> pjsip show aors

Aor: <Aor.....> <MaxContact>
Contact: <Aor/ContactUri.....> <Hash.....> <Status> <RTT(ms)...>
=====


Aor: 1001                                1
Aor: 1002                                1

Objects found: 2
test-VirtualBox*CLI>
```

Figure 1: *aors* is created


The screenshot shows the Zoiper5 login interface. On the left, there's a login form with fields for 'Username' (containing '1001@192.168.1.74') and 'Password' (containing '1001password'). Below the fields are 'Login' and 'Create account' buttons. On the right, there's a large graphic of a smiling cartoon head with a headset, and text that says 'Username and password'. Below this, it says 'If you already have a VoIP account, please enter your login credentials to the left. Most often these are provided either by your VoIP provider, or by your system administrator for your office's IP PBX.' At the bottom, a small note states: '*we will try to automatically find the necessary configuration for your account. If such does not exist in our database, you'll be asked to enter specific details.'

Figure 2: Zoiper screen for entering username and password



The screenshot shows the Zoiper5 success screen. On the left, there's a section titled 'Please wait, we are testing possible configurations'. It lists four options: 'SIP TLS' (Not found), 'SIP TCP' (Not found), 'SIP UDP' (Found), and 'IAX UDP' (Not found). The 'SIP UDP' option is selected with a radio button. Below this are 'Back' and 'Next' buttons. On the right, there's a large graphic of a smiling cartoon head with a headset, and text that says 'Success!'. Below this, it says 'We have found some transport type(s) that are available for your configuration. The default ones marked with 'Recommended' are priority ordered based on the stability and security of said protocols.'

Figure 3: Selecting transport type

```
[transport-udp]
type=transport
protocol=udp
bind=0.0.0.0
```

```
[1001]
type=endpoint
context=internal
disallow=all
allow=ulaw
auth=1001-auth
aors=1001
```

```
[1001-auth]
type=auth
auth_type=userpass
password=1001password
username=1001
```

```
[1001]
type=aor
max_contacts=1
```

```
[1002]
type=endpoint
context=internal
disallow=all
allow=ulaw
auth=1002-auth
aors=1002
```

```
[1002-auth]
type=auth
auth_type=userpass
password=1002password
username=1002
```

```
[1002]
type=aor
max_contacts=1
```

Let us see what is being done in the above code. The configuration is divided into four parts:

- **transport-udp** sets up the transport layer to handle SIP communications over UDP.
- **1001 and 1002 (endpoint sections)** define the core details for each endpoint, specifying codecs, contexts, and authentication requirements.