


Setting Up Proxmox VE on Two Servers for Storage Replication

This article covers the installation and setting up of Proxmox VE 5 on two physical servers, with ZFS for storage replication – one for a Microsoft Windows VM and another for a Linux VM.



For this fast track setup, we will use two identical servers with the following hardware configuration.

- **CPU:** 16 core Intel Xeon server 64-bit with VT enabled
- **RAM:** 32GB
- **OS HDD:** 73GB 15k enterprise HDD
- **Data HDD:** 600GB 15k enterprise HDD
- **LAN:** 1Gbps Ethernet port

Quickly installing Proxmox VE on two servers

Installing Proxmox VE 5 is rather simple and straightforward compared to other OSs.

We first need to download the Proxmox installer ISO from the link <https://www.proxmox.com/en/downloads/item/proxmox-ve-5-3-iso-installer>, and burn it on a CD.

Now follow the steps given below:

- Boot the system with the newly created bootable CD.
- At the welcome screen, choose *Install Proxmox VE* and hit *Enter*.
- Click on *I agree* to continue.
- At the next screen, use the automatic partition on the first 73GB HDD, and click on the *Next* button.
- Set the time zone and location by entering 'India'. The time zone will auto update.
- Provide a password for the root user, and enter a valid email address to get various updates and alerts about the server.
- Enter the host name, IP address, netmask, gateway and DNS. Provide all valid network details of the LAN to

access the Proxmox VE Web-management configuration interface after installation.

Set up the network with the following settings for the LAN.

For the first server:

Host: pve01.technoinfotech.com
IP: 192.168.0.11
Netmask: 255.255.255.0
Gateway: 192.168.0.1
DNS: 192.168.0.1

For the second server:

Host: pve02.technoinfotech.com
IP: 192.168.0.12
Netmask: 255.255.255.0
Gateway: 192.168.0.1
DNS: 192.168.0.1

Now, the installation process will start to install all packages from the CD. Once the installation is done, remove the installation CD and hit the reboot button.

Accessing the Web management interface

After both the servers are ready, go to the desktop to manage them. On the desktop, open Mozilla Firefox or Google Chrome, and enter the following URLs:

<https://192.168.1.11:8006> in the address bar for the first server, and <https://192.168.1.12:8006> in the address bar for the second server of another tab.