

Some files might have read-only permission to the owner, in which case we'll need to do a `chmod u+w` before modifying, deleting and overwriting it.

[1] Austrumi

Copy *austrumi.fs* and *austrumi.tgz* from */mnt/tmp1/boot/* into *mbcd/boot/*

```
$ cp /mnt/tmp1/boot/austrumi.* mbcd/boot/
```

Copy *bzImage* and *initrd.gz* from */mnt/tmp1/isolinux* to *mbcd/boot/austrumi*.

```
$ mkdir mbcd/boot/austrumi
$ cp /mnt/tmp1/isolinux/initrd.gz \
/mnt/tmp1/isolinux/bzImage mbcd/boot/austrumi
```

Austrumi searches for its files in the boot directory, so you need to keep it in there. From version 1.8.x of Austrumi, the kernel and the initial ramdisk files are located in the *austrumi/* directory in the image.

[2] Puppy Linux

Puppy Linux does not need any specific location for the files to be kept; it finds its files from any attached media. We will place the Puppy files in a directory. Copy *initrd.gz* and *vmlinuz* into *mbcd/boot/puppy*. Then copy *pup_400.sfs* and *zdrv_400.sfs* to *mbcd/Puppy*.

```
$ mkdir mbcd/boot/puppy mbcd/Puppy
$ cp /mnt/tmp2/initrd.gz \
/mnt/tmp2/vmlinuz mbcd/boot/puppy
$ cp /mnt/tmp2/pup_400.sfs \
/mnt/tmp2/zdrv_400.sfs mbcd/Puppy
```

You can download and add additional Puppy .sfs modules and keep them here.

[3] Slitaz

Now let me draw your attention to */mnt/tmp3*, the Slitaz mount point. Copy *bzImage* and *rootfs.gz* from */mnt/tmp3/boot* to *mbcd/boot/slitaz*, and copy *vmlinuz-<version>-slitaz* to *mbcd/boot*.

```
$ mkdir mbcd/boot/slitaz
$ cp /mnt/tmp3/boot/bzImage \
/mnt/tmp3/boot/rootfs.gz mbcd/boot/slitaz
$ cp /mnt/tmp3/boot/vmlinuz-*slitaz mbcd/boot
```

[4] CDlinux

Copy the *bzImage* and the *initrd* from */mnt/tmp4/CDlinux* into *mbcd/boot/cdlinux*.

```
$ mkdir mbcd/boot/cdlinux
$ cp /mnt/tmp4/CDlinux/bzImage \
/mnt/tmp4/CDlinux/initrd mbcd/boot/cdlinux
```

Then make a directory called *CDlinux* inside *mbcd* and copy the directories *extra* and *settings* into it.

```
$ mkdir mbcd/CDlinux
$ cp -r /mnt/tmp4/CDlinux/extra \
/mnt/tmp4/CDlinux/settings mbcd/CDlinux
```

After this, copy the *lang* directory into *CDlinux/* if required. When writing the config file in Phase IV, you can pass your language as the kernel parameter. CDlinux allows you to place customised packages inside the *CDlinux/local*, which gets automatically detected when booting—so you can use it if needed.

[5] DSL

Now it's time for DSL, mounted on */mnt/tmp5*. Copy *linux24* and *minirt24.gz* files from */mnt/tmp5/boot/isolinux* to *mbcd/boot/dsl*.

```
$ mkdir mbcd/boot/dsl
$ cp /mnt/tmp5/boot/isolinux/linux24 \
/mnt/tmp5/boot/isolinux/minirt24.gz mbcd/boot/dsl
```

DSL searches the cloop file (the Knoppix compressed loopback filesystem) in the *KNOPPIX/KNOPPIX* path, by default. We will relocate it and keep it in the directory *dsl/* instead, because if you decide to keep multiple Knoppix-based distros, which have the same cloop file name and path, you need to keep the cloops in different directories with different distro names. If the cloop path is altered, information about this change must be conveyed by passing a boot parameter while booting (discussed later). Copy the Knoppix cloop file from */mnt/tmp5/KNOPPIX/KNOPPIX* and place it into *mbcd/dsl*.

```
$ mkdir mbcd/dsl
$ cp -r /mnt/tmp5/KNOPPIX/KNOPPIX mbcd/dsl
```

[6] GeeXbox

Copy *vmlinuz*, *initrd.gz* and *splash.png* file from */mnt/tmp6/GEEXBOX/boot* into *mbcd/boot/geebox*.

```
$ mkdir mbcd/boot/geebox
$ cp /mnt/tmp6/GEEXBOX/boot/vmlinuz \
/mnt/tmp6/GEEXBOX/boot/initrd.gz \
/mnt/tmp6/GEEXBOX/boot/splash.png mbcd/boot/geebox
```

Then copy the whole of the */mnt/tmp6/GEEXBOX* directory into the root of our image and remove the *boot* directory inside *mbcd/GEEXBOX* as we have moved all that's required in *mbcd/boot*. (*chmod* is needed, as the directory has a permission of 444.)

```
$ cp -r /mnt/tmp6/GEEXBOX mbcd/
$ chmod -R u+w mbcd/GEEXBOX
$ rm -rf mbcd/GEEXBOX/boot
```