

```

MENU LABEL CDlinux
KERNEL /boot/cdlinux/bzimage quiet
APPEND initrd=/boot/cdlinux/initrd

LABEL sltaz
MENU LABEL Slitaz
KERNEL /boot/sltaz/bzimage rw root=/null vga=normal
APPEND initrd=/boot/sltaz/rootfs.gz

LABEL dsl
MENU LABEL Damn Small Linux
#uncomment the below line for liveCD
KERNEL /boot/dsl/linux24 ramdisk_size=100000 init=/etc/init lang=us
apm=power-off vga=791 knoppix_dir=dsl nomce noapic quiet BOOT_
IMAGE=knoppix
#uncomment the below line for liveUSB
# KERNEL /boot/dsl/linux24 ramdisk_size=100000 init=/etc/init lang=us
apm=power-off vga=791 knoppix_dir=dsl nomce noapic fromhd quiet
BOOT_IMAGE=knoppix
APPEND initrd=/boot/dsl/minitrd.gz

LABEL geexbox
MENU LABEL GeeXboX
#uncomment the below line for liveCD
KERNEL /boot/geexbox/vmlinuz root=/dev/ram0 rw rdinit=linuxrc
boot=cdrom lang=en remote=atiusb receiver=atiusb keymap=qwerty
splash=silent vga=789 video=vesafb:ywrap,mtrr hdtv quiet
#uncomment the below line for liveUSB and replace the UUID value with your
device UUID
# KERNEL /boot/geexbox/vmlinuz root=/dev/ram0 rw rdinit=linuxrc
boot=UUID=0196-F5B5 lang=en remote=atiusb receiver=atiusb
keymap=qwerty splash=silent vga=789 video=vesafb:ywrap,mtrr hdtv quiet
APPEND initrd=/boot/geexbox/initrd.gz

LABEL goblrx
MENU LABEL GoblinX Linux
KERNEL /boot/goblrx/vmlinuz vga=791 ramdisk_size=6666 root=/dev/
ram0 rw load=Muser locale=english splash=silent changes=/goblrx/.run.f
APPEND initrd=/boot/goblrx/initrd.gz

```

Now copy the JPEG image, say *splash.jpg*, to *mbcd/**boot/isolinux/*. SYSLINUX can load JPEG images directly without any modification (with the help of the *vesamenu.c32* module).

```
$ cp splash.jpg mbcd/boot/isolinux
```

If you decide not to include the *vesamenu.c32* module, you can always have a text menu. Without this *vesamenu.c32* module, the 'MENU' keywords will not be recognised and therefore no graphical menu will be displayed. It will show an error and fall back to text mode showing a *boot:* prompt asking for an OS label. Enter the label of the OS (beside the 'LABEL' field) that you want to boot and press *Enter*. To avoid memorising the label names, write a plain text file containing the OS name list and their corresponding label names and



A screenshot of the boot screen of our multi-boot CD

save it inside *mbcd/boot/isolinux/* as *list.msg*. It is printed on the screen at boot time by *DISPLAY list.msg*. The line 'F1 list.msg' displays the 'list.msg' file whenever you press F1.

An example of *list.msg* follows:

To boot the Operating System type in the keyword in the prompt and press enter

```
=====
Operating System Name  Keyword
=====
```

Astrum Linux	astrumli
Puppy Linux	puppy
CDlinux	cdlinux
Slitaz	sltaz
Damn Small Linux	dsl
GeeXboX	geexbox
GoblinX	goblrx

[2] Configuration changes for the live USB

In Phase VI we will describe how to make a bootable live USB with SYSLINUX and Grub. If you are creating a multi-boot live USB, only then make the following changes to the configuration file (Grub or SYSLINUX).

For Austrumi: replace '*dolivecd*' with '*dousb*' and for Puppy, replace '*pmmedia=cd*' with '*pmmedia=usbflash*'. For DSL, append the '*fromhd*' boot parameter in the kernel line. For GeeXBox, you need to specify the UUID of your USB device. To get the UUID of your USB partition, execute the following:

```
# blkid /dev/sdXy
```

...after replacing */dev/sdXy* with the appropriate device name in your case, and noting down the value of the UUID field. In my case, the command was *blkid /dev/sdb1* and the UUID was 0196-F5B5. Now pass the UUID by appending the following to the kernel line: