

```
touch /var/lib/mpd/db
touch /var/lib/mpd/mpdstate
touch /var/run/mpd/mpd.pid
touch /var/log/mpd/mpd.log
touch /var/log/mpd/mpd.error
chown -R mpd.mpd /var/lib/mpd
chown -R mpd.mpd /var/run/mpd
chown -R mpd.mpd /var/log/mpd
```

Now almost everything is done. Create the MPD music database as the root user. Then set 755 permissions to your home music directory.

```
mpd --create-db
chmod a+x /home/user
chmod -R a+x /home/user/music
```

You are done. You can install some MPD client, say mpc, ncmpc or Sonata (my favourite) and check if MPD runs. Start MPD as follows:

```
/etc/rc.d/mpd start
```

If everything is working fine (which it should if you follow the instructions given), then we can move on to the next section.

Setting up Icecast

Install Icecast. I am not going into the details of that one either. The following section gives the details about setting up a live Internet stream feed, which can be used as Internet radio. This article does not, in any way, condone the use of copyrighted music, podcasts or any other media files for use on the Internet. If you do not have the legal rights to stream a particular file, please do not stream it over the Internet. The author and the magazine is not responsible for any illegal action committed by the user. I'm glad we had this talk. Let's move on...

Open the file /etc/Icecast.xml in your favourite text editor and edit the file to match your needs. The following code is the sample configuration file for Icecast that I am using right now:

```
<icecast>
<limits>
<clients>100</clients>
<sources>2</sources>
<threadpool>5</threadpool>
<queue-size>524288</queue-size>
<client-timeout>30</client-timeout>
<header-timeout>15</header-timeout>
<source-timeout>10</source-timeout>
<burst-on-connect>1</burst-on-connect>
<burst-size>65535</burst-size>
</limits>
```

```
<authentication>
<!-- Sources log in with username 'source' -->
<source-password>yourPass</source-password>
<!-- Relays log in username 'relay' -->
<relay-password>yourPass</relay-password>
<!-- Admin logs in with the username given below -->
<admin-user>adminUserName</admin-user>
<admin-password>adminPass</admin-password>
</authentication>

<hostname>Local IP of your machine</hostname>

<listen-socket>
<port>Port you want to use</port>
</listen-socket>

<fileserve>1</fileserve>

<paths>
<!-- basedir is only used if chroot is enabled -->
<basedir>/usr/share/icecast</basedir>

<!-- Note that if <chroot> is turned on below these paths must both
be relative to the new root, not the original root -->
<logdir>/log</logdir>
<webroot>/web</webroot>
<adminroot>/admin</adminroot>
<alias source="/" dest="/status.xml"/>
</paths>

<logging>
<accesslog>access.log</accesslog>
<errorlog>error.log</errorlog>
<loglevel>4</loglevel> <!-- 4 Debug, 3 Info, 2 Warn, 1 Error -->
<logsize>10000</logsize> <!-- Max size of a logfile -->
</logging>

<security>
<chroot>1</chroot>

<changeowner>
<user>icecast</user>
<group>icecast</group>
</changeowner>

</security>
</icecast>
```

You need to change a few things in the above code to make the connection a more secure one. In the <authentication> tag, the default passwords and the port (8000) used by Icecast are listed. Change them to any suitable password and port. Remember, using the default port and passwords makes Icecast more prone to attacks.

Again, for more security, we will change the <chroot>