

Option	Parameters	Function	Default	Scope
Admin users	String (list of usernames)	Users who can perform operations as the root	None	Share
Valid users	String (list of usernames)	Users who can connect to a share	None	Share
Invalid users	String (list of usernames)	Users who will be denied access to a share	None	Share
Read list	String (list of usernames)	Users who have read-only access to a writable share	None	Share
Write list	String (list of usernames)	Users who have read/write access to a read-only share	None	Share
Max connections	Numeric	Maximum number of connections for a share at a given time	Zero	Share
Guest only (only guest)	Boolean	If yes, it allows only guest access	No	Share
Guest account	String (name of account)	UNIX account that will be used for guest access	Nobody	Share

Table 1

Table 2 gives the username options.

Option	Parameters	Function	Default	Scope
Username map	String (filename)	Sets the name of the username mapping file	None	Global
Username level	Numeric	Indicates the number of capital letters to use when trying to match a username	Zero	Global

Table 2

The authentication of clients is shown in Table 3.

Option	Parameters	Function	Default	Scope
Security	Domain, server, share or user	Indicates the type of security that the Samba server will use	User	Global

Table 3

The password configuration options are listed in Table 4.

Option	Parameters	Function	Default	Scope
Encrypt passwords	Boolean	If yes, enables encrypted passwords	No	Global
UNIX password sync	Boolean	If yes, updates the standard UNIX password database when users change their encrypted password	No	Global
Password chat	String (chat commands)	Sequence of commands sent to the password program	See earlier section on this option	Global
Password chat debug	Boolean	If yes, sends debug logs of the password-change process to the log files with a level of 100	No	Global
Password program	String (UNIX command)	Program to be used to change passwords	/bin/passwd%u	Global
Password level	numeric	Number of capital-letter permutations to attempt when matching a client's password	None	Global
Update encrypted password	Boolean	If yes, updates the encrypted password file when a client connects to a share with a plain-text password	No	Global
Null passwords	Boolean	If yes, allows access for users with null passwords	No	Global
smbpasswd file	String (filename)	Name of the encrypted password file	/usr/local/samba/private/smbpasswd	Global
hosts equiv	String (filename)	Name of a file that contains hosts and users that can connect without using a password	None	Global
use hosts	String (filename)	Name of a <i>hosts</i> file that allows users to connect without using a password	None	Global

Table 4