



Figure 8: Client IQN has been updated



Figure 9: The target has been discovered and the successful login has been given

Accessing iSCSI storage

- 1.) Prepare the client system to become an iSCSI initiator's node by installing the initiator utilities, setting the unique iSCSI client name and starting the iSCSI client service.
 - Install the *iscsi-initiators-utils* RPM, if not already installed, as follows:

```
# yum -y install iscsi-initiators-utils
```

- Create a unique iSCSI qualified name for the client initiators by modifying the *InitiatorName* setting in */etc/iscsi/initiatorname.iscsi*. Use the client system as the optional string after the colon.
- Enable and start the iSCSI client service, as follows:

```
# systemctl enable iscsi
```

```
# systemctl start iscsi
```



Figure 10: Newly available target

- 2.) Discover and log into the configured target from the iSCSI target server.
 - Discover and configure the iSCSI target provided by the iSCSI target server portal, as follows:

```
# iscsiadm -m discovery -t st -p 172.25.X.XX
```

- Log into the presented iSCSI target, as follows:

```
# iscsiadm -m node -T .2018-01.com.example:server -p
172.25.X.XX
```

- Identify the newly available block created by the iSCSI target login, as follows:

```
# lsblk END 
```

By: Kshitij Upadhyay

The author is RHCSA and RHCE certified, and loves to write about new technologies. He can be reached at upadhyayk04@gmail.com.

To read more stories about electronics manufacturing

Log on to

electronicsb2b.com

www.electronicshobby.com

ELECTRONICS
ELECTRONICS B2B INDUSTRY
AT THE CLICK OF A BUTTON

Log on to www.electronicseb2b.com and be in touch with the electronics B2B fraternity 24x7