

```
key.asc
```

```
apt-key add jcameron-key.asc
```

Install webmin package with the following command:

```
sudo apt-get install webmin
```

webmin runs its own secure sockets webserver, separate from apache2. Its port number, 10000, must be added to the address when typed on the address bar, like <https://xxx.xxx.x.xx:10000>.

Copy website on Raspberry Pi

With all the powerful software already installed, it is time that you do some real work. It is assumed that you already have the website ready with

you, which you would like to host on the Raspberry Pi. Otherwise, take some template from the Internet. We will use ProFTPD that we had installed earlier, to copy the website files to the required directory.

First, you need to allow root login to ProFTPD. Otherwise, you will not be able to make directories. To do that, login Raspberry Pi using putty as root. Open configuration file in nano editor at location `/etc/proftpd/proftpd.conf` and write the following lines:

```
Servname "labserver"
('labserver' needs to be replaced with the server name of your choice.)
```

```
RootLogin on
Press 'ctrl+O' (to save) and then 'ctrl+x' (to exit).
```

Now finally open the ftpuser file at location `/etc/ftuser` and enter the usernames that you want to prohibit for login using FTP servers. Now using below-mentioned commands, you have to restart the ProFTPD service to account all the changes that you have made:

```
service proftpd stop
service proftpd start
```

FTP client 'WinSCP' is used to transfer the website from your computer to Raspberry Pi by following these

steps:

1. Download and install WinSCP software, which is readily available on the Internet

2. Make a directory for your website on Raspberry Pi at `'var/www/saylab'`

3. Login to WinSCP, navigate to this directory and copy the website to Raspberry Pi using drag-and-drop operation (see Fig. 16)

4. Now open any browser on your computer and type `'http://xxx.xxx.x.xx/lab'` in the address bar. You will see your website.

After all the steps, the website will be available on the local network and now the only thing left is to make your website available outside the network too. For that you have to make some changes in your router settings:

1. You should have a static IP and ADSL router. Dial-up will not work.

2. Write `'ipconfig'` in the command prompt and note the IP address list after 'Default Gateway.'

3. Put this IP address in the address bar of any browser to access the router.

4. Now navigate the pages and go to the one that has setting for port forwarding. You need to direct all port-80 packets to Raspberry Pi.

5. Create a new record if necessary and enter the IP address of Raspberry Pi and the port number as 80.

6. Select option 'TCP+ UDP' in the settings.

7. Save the settings and reboot the router.

Now you need the WAN IP to access your website from outside your local network. You can get this WAN IP from the website `'www.whatsmymip.com'` and note it down. Now type this address in the address bar of any Web browser. You should see your website. ●

The author is working as an assistant manager at Samtel Avionics & Defence Systems




Fig. 15: WinSCP




Fig. 16: Copy the website by drag-and-drop operations