

Dynamic Navigation Between Steps

Dynamic navigation is an additional way of defining navigation between steps in a DFC that contains a complex step flow. You can govern the flow by setting the value of one of the function outputs in the step called the *Dynamic Navigation Output*.

The Dynamic Navigation Output can be chosen in the **Advanced** tab of the step properties pane.

You can disable the dynamic navigation output with use of the `EnableDynamicNavigation` key located in the `ProcessBuilder` section of the Central Configuration file. For details, see [Central Configuration Documentation](#).

Dynamic Navigation Output value	Performed action
STOP	The system should go to the stop node, as if the navigation contained an arrow going to the stop node.
LOGOUT	The system should go to the logout node, as if the navigation contained an arrow going to the logout node.
ABANDON	The system should go to the abandon node, as if the navigation contained an arrow going to the abandon node.
BACK	The system should go to the last step that was marked as return step. If there is no step in the execution history with this flag set, the system should stay on the same screen.
00000000-0000-0000-0000-000000000000	The system should go to the step with an FUID equal to the one provided, as if the navigation contained an arrow going to this step. The system has to validate that the FUID is correct, i.e., that there exists a step in the current DFC with this FUID. If the validation fails, an error is shown stating that the next step identifier is invalid.
(empty)	The system should use the static navigation configuration as defined in the DFC.
(other)	The system should display an error stating that the dynamic navigation failed due to an invalid next step identifier.