

Extensible Access Control Function

The EAC function enables requesting and receiving data access permissions.

Adding the Extensible Access Control Function

Prerequisites

The configuration must be set up in the `ExtensibleAccessControlConfiguration.xml` file in the `CentralConfiguration` folder.

In `ExtensibleAccessControlConfiguration.xml` you can specify the Request Types, which can then be selected in the Request Message Type dropdown, Inputs for each Request types, and the `MethodName` of the REST Service.

Example configuration:

```
<?xml version="1.0"?>
<ExtensibleAccessControlConfigurations xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" >
  <Request RequestType = "CheckWOAcces">
    <Inputs>
      <Input>
        <Name>View</Name>
        <Type>String</Type>
      </Input>
      <Input>
        <Name>doc123</Name>
        <Type>String</Type>
      </Input>
    </Inputs>

    <MethodName>GetPermitResult</MethodName>

    <MessageBody>
      <![CDATA[
        <?xml version="1.0" encoding="UTF-8"?>
        <xacml-ctx:Request ReturnPolicyIdList="true" CombinedDecision="false" xmlns:xacml-
        ctx="urn:oasis:names:tc:xacml:3.0:core:schema:wd-17">
          <xacml-ctx:Attributes Category="urn:oasis:names:tc:xacml:3.0:attribute-category:action" >
            <xacml-ctx:Attribute AttributeId="actionId" IncludeInResult="true">
              <xacml-ctx:AttributeValue DataType="http://www.w3.org/2001/XMLSchema#string">@View@</xacml-
              ctx:AttributeValue>
            </xacml-ctx:Attribute>
          </xacml-ctx:Attributes>
          <xacml-ctx:Attributes Category="urn:oasis:names:tc:xacml:3.0:attribute-category:resource" >
            <xacml-ctx:Attribute AttributeId="resource-id" IncludeInResult="true">
              <xacml-ctx:AttributeValue
              DataType="http://www.w3.org/2001/XMLSchema#string">@doc123@</xacml-ctx:AttributeValue>
            </xacml-ctx:Attribute>
          </xacml-ctx:Attributes>
        </xacml-ctx:Request>
      ]]>
    </MessageBody>
  </Request>
</ExtensibleAccessControlConfigurations>
```


<MessageBody> is a message template that is sent to the EAC service. The attribute values are replaced by the input values that is inserted during the runtime.

The attribute values in the Message Body must be preceded and followed by @.

Multiple Request Types can be configured in the ExtensibleAccessControlConfiguration.xml.

To Add the Extensible Access Control Function

Drag the Extensible Access Control function from the [Toolbox](#) to the Function Navigation diagram, or double-click the Extensible Access Control icon in the Toolbox. The system will automatically add the required Inputs based on the configuration defined in the ExtensibleAccessControlConfiguration.xml.



EAC Function Inputs

Input	Description
CustomHeaders	A custom information added to the EAC request header.

EAC Function Outputs

Output	Description
Permission	Permission to access the data or object.
DecisionType	Possible decision types: ▶ Permit ▶ Deny ▶ Indeterminate ▶ NotApplicable
ResultContent	The response message from the service contents.

EAC Function Properties

General

Name

ExtensibleAccessControl2

Description

Type

Extensible Access Control

☐ Log Events

Extensible Access Control

Request Message Type

CheckWOAcces

☒ Block process when an error occurs

Field	Description
Request Message Type	The type of data the EAC function will try to get the access to. Multiple request message types can be configured in the ExtensibleAccessControlConfiguration.xml file.
Block process when error occurs	If the checkbox is selected, the DFC will stop when an error is returned from the EAC service. Otherwise, the error will be ignored and the DFC will continue uninterrupted, but the permission to access the data will be denied.