#### LAB 2



# ĐỊA CHỈ IPv4 - CHIA MẠNG CON CẤU HÌNH SWITCH VÀ ROUTER - VẠCH ĐƯỜNG TĨNH

Họ tên và MSSV: Nguyễn Hữu Tường - B1910480

Nhóm học phần: CT29306

- Các sinh viên bị phát hiện sao chép bài của nhau sẽ nhận 0đ cho tất cả bài thực hành của môn này.
- Bài nộp phải ở dạng PDF, hình minh họa phải rõ ràng chi tiết. Hình minh hoạ chỉ cần chụp ở nội dung thực hiện, không chụp toàn màn hình.

## 1. Cấu hình địa chỉ IPv4

Xem video hướng dẫn và thực hiện các yêu cầu sau:


Sử dụng file Lab02-01 - IPv4 Addresses.pkt, thực hiện:

- Cấu hình hostname cho R1.
- Sử dụng lệnh show hiển thị thông tin của các interface của R1.
- Cấu hình địa chỉ IP phù hợp cho các interface của R1 và bật các interface đó lên.
   Cấu hình các mô tả cho các interface.
- Sử dụng lệnh show để hiển thông tin các interface của R1.
- Hiển thị running configuration (chụp hình minh họa).

```
interface GigabitEthernet0/0
 description ## to swl ##
 ip address 15.255.255.254 255.0.0.0
 duplex auto
 speed auto
interface GigabitEthernet0/1
 description ## to SW2 ##
 ip address 182.98.255.254 255.255.0.0
duplex auto
speed auto
interface GigabitEthernet0/2
 description ## to SW3 ##
 ip address 201.191.20.254 255.255.255.0
 duplex auto
 speed auto
interface Vlanl
no ip address
shutdown
ip classless
ip flow-export version 9
```

- Cấu hình địa chỉ IP cho PC1, PC2, PC3

- Từ PC1 ping tới PC2 và PC3 để kiểm tra nối kết (chụp hình minh họa).



# 2. Cấu hình interface của switch và router

Xem <u>video hướng dẫn</u> và thực hiện các yêu cầu sau: Sử dụng file *Lab02-02 - Interface Configuration.pkt*, thực hiện:

- Cấu hình hostname cho R1, SW1, và SW2.
- Cấu hình địa chỉ IP phù hợp cho R1, PC1, PC2, PC3, PC4.
- Cấu hình tốc độ và chế độ duplex cho các interface nối kết tới các thiết bị mạng khác (switch, router, KHÔNG phải PC).
- Cấu hình mô tả phù hợp cho mỗi interface.
- Tắt các interface không nối kết tới các thiết bị khác.
- Hiển thị running configuration (chụp hình minh họa).


```
₽ R1
  Physical Config CLI Attributes
   interface GigabitEthernet0/0
   description ## to SWl ##
   ip address 172.16.255.254 255.255.0.0
   duplex full
   speed 1000
   interface GigabitEthernet0/1
   description ## not in use ##
   no ip address
   duplex auto
   speed auto
   shutdown
   interface GigabitEthernet0/2
   description ## not in use ##
   no ip address
   duplex auto
   speed auto
    shutdown
   interface Vlanl
   no ip address
   shutdown
   ip classless
  ip flow-export version 9
```

```
Physical Config CLI Attributes

interface FastEthernet0/1
description ## to end hosts ##
!
interface FastEthernet0/2
description ## to end hosts ##
!
interface FastEthernet0/3
description ## not in use ##
shutdown
!
interface FastEthernet0/4
description ## not in use ##
shutdown
!
interface FastEthernet0/5
description ## not in use ##
shutdown
!
interface FastEthernet0/5
description ## not in use ##
shutdown
!
```

```
SW1
  Physical Config CLI Attributes
   interface FastEthernet0/20
   description ## not in use ##
   shutdown
   1
   interface FastEthernet0/21
   description ## not in use ##
   shutdown
   interface FastEthernet0/22
   description ## not in use ##
   shutdown
   interface FastEthernet0/23
   description ## not in use ##
   shutdown
   interface FastEthernet0/24
   description ## not in use ##
   shutdown
   interface GigabitEthernet0/1
   description ## to Rl ##
   duplex full
   speed 1000
   interface GigabitEthernet0/2
   description ## to SW2 ##
   duplex full
   speed 1000
   interface Vlan1
   no ip address
    shutdown
```

```
SW2
          Config CLI Attributes
 Physical
                                IOS Comman
  interface FastEthernet0/1
   description ## to end hosts ##
  interface FastEthernet0/2
  description ## to end hosts ##
  interface FastEthernet0/3
  description ## not in use ##
   shutdown
  interface FastEthernet0/4
   description ## not in use ##
   shutdown
  interface FastEthernet0/5
   description ## not in use ##
   shutdown
  interface FastEthernet0/6
   description ## not in use ##
   shutdown
```




# 3. Cấu hình vạch đường tĩnh (static route)

Xem video hướng dẫn và thực hiện các yêu cầu sau:

Sử dụng file Lab02-03 - Configuring Static Routes.pkt, thực hiện:

- Cấu hình PC và router theo sơ đồ mạng (không cần cấu hình các switch). Lưu ý cấu hình gateway cho các PC.
- Cấu hình vạch đường tĩnh (static route) cho các router sao cho PC1 có thể ping thành công tới PC2. Chụp hình minh họa.



Hiển thị running configuration (chụp hình minh họa).

### Router 1:

```
interface GigabitEthernet0/0
 description ## to R2 ##
 ip address 192.168.12.1 255.255.255.0
 duplex auto
 speed auto
interface GigabitEthernet0/1
 description ## to SWl ##
 ip address 192.168.1.254 255.255.255.0
 duplex auto
 speed auto
interface GigabitEthernet0/2
no ip address
 duplex auto
speed auto
 shutdown
interface Vlan1
no ip address
shutdown
ip classless
ip route 192.168.3.0 255.255.255.0 192.168.12.2
ip flow-export version 9
```

### Router 2:

```
interface GigabitEthernet0/0
description ## to Rl ##
ip address 192.168.12.2 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/1
description ## to R3 ##
ip address 192.168.13.2 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/2
no ip address
duplex auto
speed auto
shutdown
interface Vlan1
no ip address
shutdown
ip classless
ip route 192.168.1.0 255.255.255.0 GigabitEthernet0/0
ip route 192.168.3.0 255.255.255.0 192.168.13.3
ip flow-export version 9
```

Router 3:

```
interface GigabitEthernet0/0
description ## to R2 ##
 ip address 192.168.13.3 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/1
 description ## to SW2 ##
 ip address 192.168.3.254 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/2
no ip address
duplex auto
speed auto
shutdown
interface Vlanl
no ip address
shutdown
ip classless
ip route 192.168.1.0 255.255.255.0 192.168.13.2
ip flow-export version 9
```

# 4. Xử lý lỗi trong cấu hình vạch đường tĩnh


Xem video hướng dẫn và thực hiện các yêu cầu sau:

Sử dụng file Lab02-04 - Troubleshooting Static Routes.pkt, thực hiện:

- Hiện tại PC1 và PC2 không thể ping được nhau bởi vì có cấu hình sai trên mỗi router. Tìm các cấu hình sai và sửa chúng để cho PC1 và PC2 có thể ping được nhau.
- Hiển thị running configuration (chụp hình minh họa).

```
🥐 R1
          Config CLI Attributes
 Physical
                                IOS Command Line Interface
  interface GigabitEthernet0/0
  description ## to R2 ##
  ip address 192.168.12.1 255.255.255.0
  duplex auto
  speed auto
 interface GigabitEthernet0/1
  description ## to SW1 ##
  ip address 192.168.1.254 255.255.255.0
  duplex auto
  speed auto
 interface GigabitEthernet0/2
  no ip address
  duplex auto
  speed auto
  shutdown
 interface Vlan1
  no ip address
  shutdown
 ip classless
 ip route 192.168.3.0 255.255.255.0 192.168.12.2
 ip flow-export version 9
```

```
₽ R2
 Physical
          Config CLI Attributes
                                IOS Command Line Interface
 interface GigabitEthernet0/0
  description ## to R1 ##
  ip address 192.168.12.2 255.255.255.0
  duplex auto
  speed auto
 interface GigabitEthernet0/1
  description ## to R3 ##
  ip address 192.168.13.2 255.255.255.0
  duplex auto
  speed auto
  interface GigabitEthernet0/2
  no ip address
  duplex auto
  speed auto
  shutdown
 interface Vlanl
  no ip address
  shutdown
 ip classless
 ip route 192.168.1.0 255.255.255.0 192.168.12.1
 ip route 192.168.3.0 255.255.255.0 GigabitEthernet0/1
 ip flow-export version 9
```



# 5. VLSM

Xem video hướng dẫn và thực hiện các yêu cầu sau:

Sử dụng file Lab02-05 - VLSM.pkt, thực hiện:

- Chia mạng con cho nhánh mạng 192.168.5.0/24 để có thể cung cấp đủ địa chỉ cho các LAN và nối kết giữa R1 và R2.
- Lấy địa chỉ IP khả dụng đầu tiên của mỗi mạng con cấu hình cho PC trong mỗi LAN.
- Láy địa chỉ IP khả dụng cuối cùng của mỗi mạng con cấu hình cho interface của router trong mỗi LAN.
- Cấu hình vạch đường tĩnh cho mỗi router để các PC có thể ping lẫn nhau.
- Hiển thị running configuration (chụp hình minh họa).

