

3/2/2010

WS-ARC SERVICE CONFIGURATION MANUAL

Martin Skou Andersen*

^{*}skou@nbi.dk

Contents

1	Intr	roduction	3
	1.1	How to read this manual	3
2	INI	configuration	3
	2.1	Examples	4
		2.1.1 Echo service	4
		2.1.2 Other service	4
	2.2	Limitations	4
3	$\mathbf{X}\mathbf{M}$	IL configuration	5
	3.1	Overview	5
	3.2	Service configuration	5
	3.3	Message Chain	5
		3.3.1 TCP MCC	6
		3.3.2 TLS MCC	7
		3.3.3 GSI MCC	7
		3.3.4 HTTP MCC	8
		3.3.5 SOAP MCC	8
		3.3.6 Plexer	8
	3.4	Security Handlers	8
		3.4.1 ARC Authorization	9
		3.4.2 Identity Mapping	9
		3.4.3 Delegation Collector	9
		3.4.4 Delegation Handler	9
		3.4.5 Username Token	9
		3.4.6 Username Token	9
	3.5	Policy Decision Points	9
	3.6	General Daemon Configuration	9
	3.7	Examples	10
		3.7.1 Echo Service	10
4	Pro	ofiles	11
5	The	e arched daemon	13
\mathbf{A}	List	t of standard profiles in WS-ARC	13
-		-	13
			14
			14
		Charon	14
			14
		-	

	A.7 Testing	15
]	B Profile attributes naming convention	15
•	C XML Schemas	16
	C.1 General Daemon Schema	16
	C.2 Loader Schema	19
	C.3 TCP Schema	22
	C 4 TLS Schema	24

1 Introduction

The Web Service (WS) Advanced Resource Connector (ARC) provides a great deal of services which all share a common configuration interface. One or more services can be specified in a configuration and the arched daemon should then be used for starting the service(s). The configuration should be specified in a file using either the relatively simple INI format, or the more complex XML format.

INI configuration is the recommended way of configuring services for people who are new to ARC or unfamiliar with WS-ARC configuration. However it is limited in the sense that it relies on profiles. A profile is a configuration template setup for one or more services, and common use case profiles exist for most services and are installed per default. The limitation lies in the fact that only services and options which are specified in the profile can be configured in INI configuration, however the installed profiles should give enough flexibility for common use cases. For a detailed description on INI configuration see section 2. Profiles are further discussed in section 4.

XML configuration is the core format of WS-ARC configuration – it is used internally – and thus it gives full flexibility when configuring services. A detailed description of XML configuration can be found in section 3.

The arched daemon, which is used to start WS-ARC services according to the configuration is briefly discussed in section 5.

1.1 How to read this manual

This manual is divided into the three independent sections INI configuration, XML configuration and Profiles, and these can be read independent of each other. Additionally the arched section describe the command with the same name.

It should be noted that words typeset with the typewriter font should be typed as written.

2 INI configuration

As mentioned in the introduction, INI configuration directly relies on profiles, and a profile is a configuration template setup for one or more services. So when creating a INI configuration file a choice of profile must be made. Only one profile can be used in a given INI configuration. A standard WS-ARC installation comes with a set of profiles and the list in appendix A gives a short description of these. The profiles will per default be installed into the /usr/share/arc/profiles folder, where it is also possible to find an example INI configuration file for each of the profiles.

A INI configuration file basically consist of sections, attribute-value pairs and maybe comments and blank lines. In the following code-listing the syntax of an INI configuration file is shown:

```
# A comment
[ common ]
profile = <path-to-profile>

<attribute> = <value>
...
...
# Another comment
[ <section-name> ]
<attribute> = <value>
...
[ <another-section> ]
<attribute> = <value>
...
[ <another-section> ]
<attribute> = <value>
...
...
...
```

A section is specified by putting the name of the section inside brackets ([and]), where the left bracket ([) must be the first non white space character on the line. Any white space character after the left bracket and before the right will not be part of the section name. Every attribute-value pair belongs to the section which has be been defined previously. If the file starts without declaring a section, then following attributes will belong to the common section. Multiple sections with identical names are different sections, except for the common section, which is special in this respect and if multiple common sections exist these will be considered as one.

The profile attribute is also a special, as it is used to indicate which profile the INI configuration uses, and its value should be the absolute path to the profile file. The profile attribute must be located in the common section. If multiple profile attributes exist only the first attribute will be used.

Attribute-value pairs are defined by specifying the name of the attribute followed by an equal sign and then the value the attribute should take. It is the first equal sign which separates the attribute from the value. If a line, not defining a section, does not contain an equal then it will be ignored and if it contains multiple equal signs then all but first equal sign will be part of the value. Any white space before and after the attribute and value will be ignored. Only attributes which have been defined in the selected profile will be consideren by arched. For each profile in WS-ARC a corresponding INI configuration file exist which defines sensible values and at the time list all configurable attributes. When it comes to multiple attributes with identical names defined in the same section, it is the selected profile which determines if multiple attributes is allowed and will be interpreted or not. It is possible that attributes from one section can override attributes from another section, however this behaviour is completely determined by the profile.

Comments in the INI configuration file are specified by letting the first non white space character be the sharp character (#), and these will be ignored by arched.

2.1 Examples

2.1.1 Echo service

```
profile = /usr/share/arc/profiles/EchoService.xml

pidfile = /tmp/arched.pid
logfile = /tmp/arched.log
loglevel = INFO

port = 60000

cacert = /etc/grid-security/certificates
host_cert = /etc/grid-security/hostcert.pem
host_key = /etc/grid-security/hostkey.pem

[ echo ]
prefix = {{
suffix = }}
```

2.1.2 Other service

2.2 Limitations

Configuring WS-ARC services in INI format may pose some limitations, since this configuration format depend on profiles. If one wants to configure a service setup which is not covered by any of the available profiles, it is simply not possible to configure that service setup in INI format and one has to use the XML format described in section 3. It should however be noted that it is easy to switch from INI to XML format since the arched command provide a way to convert a INI configuration into XML. See section 5 for further details.

3 XML configuration

3.1 Overview

XML configuration in WS-ARC provides full flexibility for configuring services, and to construct an adequate configuration one need to address the following subjects. If not done already, a choice on which service(s) being setup need to be made and a short discussion of the available WS-ARC services is given in section 3.2. Upon the choice of service(s) the proper message chain need to be configured and a discussion about message chains is given in section 3.3. Most people also want some kind of security setup capable of allowing/denying certain users, which can be done with security handlers and is discussed in section 3.4. Common configuration options like specifying plugins required for instance by the message chain, and configuring logging, is discussed in section 3.6. In section 3.7 example XML configuration files are given.

3.2 Service configuration

The following services are part of WS-ARC and specific configuration details for these are given in the respective references below:

A-REX A-REX

Chelonia

ISIS

Charon

hopi hopi, a lightweight HTTP webserver, is described in details in %% REFERENCE.

3.3 Message Chain

To configure WS-ARC services, a basic knowledge about how these are communicating with clients or other services is needed. WS-ARC uses a chain of message components (MCCs) which serves different levels of functionality. In one end it accepts messages from an interface and in the other a service processes them and produce a response. Two types of MCCs exist, and they differ in that the first type should be able to listen on some interface for messages, while the other simply receives messages from another MCC. The MCC then process the message and pass it on to a single or multiple other MCCs or services. MCCs should be configured using the XML element Component, where the name attribute specifies the MCC to use. The following MCCs is part of WS-ARC:

tcp.service Listens on the TCP interface, see section 3.3.1,

tls.service Adds encryption layer to communication, see section 3.3.2,

http.service Processes HTTP messages, see section 3.3.4,

soap.service Processes SOAP messages, see section 3.3.5.

Additionally a special MCC, the Plexer, exist which is able to pass messages to different components simply based on the endpoint the messages was sent to, and it should should be configured using the Plexer element, see section 3.3.6. In the end of the chain a service should be specified, using the Service element, where the name attribute indicates the given service.

A working configuration should then link a set of MCCs and services, starting with a MCC that receives messages from some interface. The MCCs and services should be uniquely identifiable, by setting the id attributes of these elements. A MCC links to another or several MCCs or services using the next element, where the id attribute specifies the id of that MCC or service. The message chain should be contained in the root element ArcConfig, which is shown in the conceptual configuration example below:

For readability the message chain can be grouped into a Chain element in one or more levels.

3.3.1 TCP MCC

The TCP message component is named tcp.service and should be the first component in a chain. It is used to setup a server socket which will listen for incoming connections. The socket can be configured using the Listen element, which can occur multiple times and under each element the following child elements can be specified:

Interface This element specifies the interface which socket should listen on. If this element is not specified then the socket will listen on all available interfaces.

Port The port which the socket should bind to should be specified with this element. If no port is specified an error will be reported and this Listen element will be ignored.

Version The IP version can be specified by this element, and by default both version 4 and 6 will be used. It is possible to specify version 4 or 6 only.

NoDelay By default Nagle's algorithm is used for sending data, however if the NoDelay element is set to true data will be sent when ready. This is mainly used for optimizing connections for communication patterns which involve a lot of very short messages exchanged by service and client.

Timeout Specifies how much time, in seconds, data sending or receiving may take. If time is exceeded MCC reports error and in most cases connection is dropped. The default value is 60 seconds.

It is also possible to put a limit on number of incoming connections, and how these should be handled if the limit is reached. The limit can only be put on all configured interfaces, and not per interface. The Limit element specifies the limit on incoming connections, and the drop attribute specifies whether new connections, above the limit, will be put on hold (default) or if they should be dropped, which is specified by setting the attribute to true.

An example of a TCP MCC configuration using the described elements is shown below:

```
<Component name="tcp.service" id="tcp">
 <Listen>
    <Interface>w.x.y.z</Interface>
    <Port>44444</Port>
    <Version>4</Version>
    <NoDelay>true</NoDelay>
    <Timeout>120</Timeout>
  </Listen>
  <Listen>
    <Interface>a:b:c:d:e:f:g:h</Interface>
    <Port>55555</Port>
    <Version>6</Version>
    <NoDelay>false</NoDelay>
    <Timeout>20</Timeout>
  <Limit drop="true">30</Limit>
</Component>
```

. . .

3.3.2 TLS MCC

A security layer can be configured with the TLS MCC, named tls.service, and it should be put on top of a TCP MCC. By default it is able to understand the SSLv2 (hadshake only), SSLv3 and TLSv1 protocols, however the Handshake element can be used to specify another behaviour. The supported values for the Handshake element are TLS (default) and SSLv3, where specifying the latter will configure a MCC which only understand the SSLv3 protocol. If other values than the mentioned ones are given, then TLS will be used.

For the TLS MCC to function, it should have access to a host key-certificate pair. The key should be the private one, and it should not be password protected. The path to the key-certificate pair can be specified by using the KeyPath and CertificatePath elements. If the KeyPath element is not specified the default path /etc/grid-security/hostkey.pem will be used, and likewise if the CertificatePath element is not specified the default path /etc/grid-security/hostcert.pem will be used. The supported key and certificate formats are PEM and DER.

When establishing a connection with a client, the client certificate are per default verified against the Certificate Authority (CA) certificates, known to the TLS MCC. The CA certificates used for verification can be specified with either the CACertificatesDir or the CACertificatePath element, or both elements can be used. The CACertificatesDir element should point to a directory containing one or more CA certificates (in PEM format). The files should each contain exactly one certificate, and should be named by the hash value of the CA subject name. CA certificates provided by NorduGrid uses this option. The CACertificatePath element should point to a file containing one or more CA certificates (in PEM format) identified by:

```
----BEGIN CERTIFICATE----
... (CA certificate in base64 encoding) ...
----END CERTIFICATE----
```

sequences. If both elements have been specified, CA certificates will first be looked up in the file pointed to by the CACertificatePath element and then in the directory pointed to by the CACertificatesDir element. If none of the two elements have been specified, then the CACertificatesDir element will be initialised to the /etc/grid-security/certificates location. Client certificate verification can also be skipped, which is done by setting the ClientAuthn element to false.

If element CACertificatesDir have attribute PolicyGlobus set to "true" additional verification of client credentials is performed. Client credentials are restricted to be signed by specific Certification Authorities as specified in additional configuration files. Those files are stored in the location specified by the element CACertificatesDir and have names made of the hash of the subject of CA certificate followed by .signing_policy suffix. Information about format of those files may be found at http://dev.globus.org/wiki/Signing_Policy

3.3.3 GSI MCC

At its purpose MCC is similar to TLS described in section 3.3.2. It provides security layer using Globus implementation of GSS-API and corresponding communication protocol.

Its configuration element KeyPath and CertificatePath are identical to those of TLS MCC. This MCC is implemented using libraries of Globus Toolkit and its functionality and requirements are better to be described by descrition of Globus gssapi library.

Use of this MCC is not recommended due to non-standard origin of underlying protocol.

3.3.4 HTTP MCC

The HTTP protocol is supported by the HTTP MCC named http.service, and it should either be put on top of the TCP or TLS MCC. A working configuration of this MCC is simple, since it should only use the next element which must have a value equal to one of the HTTP request methods. An example of a HTTP MCC configuration is shown below.

```
...
<Component name="http.service">
    <next id="component1">GET</next>
    <next id="component2">POST</next>
    <next id="component3">PUT</next>
    </Component>
...
```

3.3.5 SOAP MCC

SOAP is supported by the SOAP MCC, named soap.service. It parses and processes incoming messages as SOAP messages. This component should be put right after the HTTP MCC in the message chain. The component is needed by most of the services in WS-ARC. The only option which should be configured for the SOAP MCC is to which component or service the valid SOAP messages should be directed to, and it is done with the next element as for the other components.

3.3.6 Plexer

The Plexer is a special MCC which filters messages based on their URL endpoints. One or more regular expressions (POSIX extended) should be defined using one or more next elements, and these will then be used to filter incoming messages, thus forwarding messages, where the path of the endpoint URL matched a given regular expression, to the component or service specified by the id attribute of the corresponding next element. At the first match the message will be forwarded to the respective component or service and no more expressions will be tried. If a message did not match any of the regular expressions then it is discarded and an error code is returned to the client. An example of a Plexer configuration is shown below.

3.4 Security Handlers

Security Handlers are components which extract security related properties of the message, collect then and use for making authorization decisions.

The Security Handlers are assigned MCCs and are arranged in queues. Each queue is processing specific messages. Usually MCCs implement two queues named "incoming" and "outgoing" for the messages going through chain to service and returning back respectively.

The Security Handlers in each queue are applied sequentially and if any produces negative result processing stops are error is raised.

The Security Handlers are added to MCCs through SecHandler configuration element put inside Component or Service elements. The name attribute specifies which plugin to be used. And queue is specified by event attribute. Each configured instance can be optionally assigned identifier through id attribute. The content of SecHandler is specific for every kind of plugin. Example is below:

3.4.1 ARC Authorization

This Security Handler applies set of Policy Decision Point (PDP) element to the message and then produces decision result using combining algorithm specified in action attribute of SecHandler element. For desciption of PDP elements see section 3.5.

Available combining algorithms are:

breakOnDeny - processing stops when PDP returns Deny decision. The SecHandler produces negative result. This is a default algorith.

breakOnAllow - processing stopr when PDP return Allow decision. The SecHandler produces positive result.

breakAlways - processing stops after first PDP. Produced result is used as result of SecHandler.

breakNever - all PDPs are applied. Result of last PDP is used as result of SecHandler.

- 3.4.2 Identity Mapping
- 3.4.3 Delegation Collector
- 3.4.4 Delegation Handler
- 3.4.5 Username Token
- 3.4.6 Username Token
- 3.5 Policy Decision Points

3.6 General Daemon Configuration

The following options configures the arched daemon, and thus applies to all services. Some of the options can also be set using command line arguments, and if used these will override the configuration file options. See section 5 for a description of the arched daemon.

Under the Server element the file to store the PID in, can be specified using the PidFile element, if not specified the PID will be stored in the file /var/run/arched.pid. This options can also be set using a command line argument. If the Foreground element is present under the Server element, arched will run in foreground and thus the PidFile element will be ignored. It is also possible to specify that arched should run in foreground on the command line, however it is not possible to specify that it should run as a daemon, if configured to run in foreground in the configuration file. Also under the Server the user and group owning the arched process can be specified, which is accomplished with the User and Group elements. These can also be set on the command line.

Logging options should be specified under the Logger element under the Server element. The File element specifies which file to write log messages to and if not present log messages will be written to the

/var/log/arched.log file. Each log message is associated with a log level which indicates the serverity of the message. The following log levels exist in WS-ARC, ordered by serverity: FATAL, ERROR, WARNING, INFO, VERBOSE and DEBUG. With the Level element the level of messages being reported can be specified. Log messages with a higher or same level as specified by the Level element will be written to the log file. The default log level is WARNING.

By default the log file is not limited in size, neither will any log rotation be done. The Maxsize and Backups elements can be used to change this behaviour. The Maxsize element sets the maximum file size of the log file in bytes, while the Backups element specifies the number of files used for log rotation. When the size of the log file exceeds the limit specified by the Maxsize element the log file is renamed to <log-file>.1. If this file exist it is renamed to <log-file>.2 and so forth up to the number specified by Backups, which means that the last file will be deleted. The log file size is only allowed to exceed the specified limit by the size of one log message. If the Maxsize element have been specified and no Backups element is specified then log rotation will not be carried out, thus the log file is truncated when the limit is exceeded.

Plugins which should be used later in the configuration should be specified under the Plugins element where the Name element specifies the name of the plugin. The Path element under the ModuleManager element specifies where to locate the plugins.

The following example show the use of the above configuration options:

```
<?xml version="1.0"?>
<ArcConfig>
 <Server>
    <PidFile>/tmp/arched.pid</PidFile>
    <User></User>
    <Group></Group>
    <Logger>
      <File>/tmp/arched.log</File>
      <Level>WARNING</Level>
      <MaxSize>1000000</MaxSize>
      <Backups>5</Backups>
    </Logger>
  </Server>
  <ModuleManager>
    <Path>/usr/lib/arc</Path>
  </ModuleManager>
  <Plugins>
    <Name>plugin1</Name>
    <Name>plugin2</Name>
 </Plugins>
</ArcConfig>
```

3.7 Examples

3.7.1 Echo Service

```
<cfg:Level>WARNING</cfg:Level>
    </cfg:Logger>
  </cfg:Server>
  <ModuleManager>
    <Path>/usr/lib/arc</Path>
  </ModuleManager>
  <Plugins>
    <Name>mcctls</Name>
    <Name>mcchttp</Name>
    <Name>mccsoap</Name>
    <Name>mcctcp</Name>
  </Plugins>
  <Chain>
    <Component name="tcp.service" id="tcp">
      <next id="http"/>
      <tcp:Listen>
        <tcp:Interface>0.0.0</tcp:Interface>
        <tcp:Version>4</tcp:Version>
      </tcp:Listen>
    </Component>
    <Component name="http.service" id="http">
      <next id="soap">POST</next>
      <next id="plexer">GET</next>
    </Component>
    <Component name="soap.service" id="soap">
      <next id="plexer"/>
    </Component>
    <Plexer id="plexer">
      <next id="echo">/Echo</next>
    <Service name="echo" id="echo">
      <echo:prefix>[</echo:prefix>
      <echo:suffix>]</echo:suffix>
    </Service>
  </Chain>
</cfg:ArcConfig>
```

4 Profiles

In WS-ARC the concept of profiles have been introduced. A profile is a complete XML configuration template, for a specific service setup and it is used when configuring services in INI format. The core of WS-ARC uses an XML struture for service initialization, which makes the XML format the apparent choice for configuration. However the XML language is not simple and easy to use, which is why WS-ARC utilizes profiles, namely to provide a configuration format (the INI format) easy to use.

To write a profile, some knowledge on the INI (see section 2) and XML configuration formats (see section 3) is needed. Not necessaray to say, knowledge on the desired service setup is also needed. A XML configuration file is only a profile if it defines a option mapping from INI format to XML, thus making it possible to utilise the XML configuration through the INI format.

Two XML attributes have been introduced to be able to create a mapping, and these are inisections and initag. XML elements which should be configurable in INI format must specify these attributes. The initag attribute defines the name of the tag which represent the respective XML element in the INI configuration file, and the inisections attribute is used to specify, as a space separated list, which sections the tag can occur in. The list is ordered, in the sense that the listed sections is searched, in the specified order, for the tag specified by the initag attribute, and if found in a section no further sections will be searched. Only leaf XML elements (elements with no child elements) should be mapped, mapping non leaf element result in a undefined behaviour. A profile example of a XML element mapping is shown in the listing below:

ElementMapping.xml

And this example profile can then be utilised in a INI configuration file as:

ElementMapping.ini

```
profile=ElementMapping.xml
logfile=/etc/arc/arched.log
...
[ special ]
logfile=/var/arc/arched.log
...
```

And the resulting XML configuration will look like:

```
...
<Server>
...
<Logger>
<File>/var/arc/arched.log</File>
...
</Logger>
</Server>
...
```

To be able to map XML attributes the use of a new XML element AttributeRepresentation have been introduced. The element should have three attributes set, the two attributes inisections and initag used as described above, and a new attribute id which specifies which attribute of the parent element is being mapped. A profile example of a XML attribute is shown in the listing below:

AttributeMapping.xml

And this example profile can then be utilised in a INI configuration file as:

AttributeMapping.ini

```
profile=AttributeMappingExample.xml
drop=true
...
```

And the resulting XML configuration will look like:

```
...
<Component name="tcp.service">
...
<Limit drop="true">100</Limit>
</Component>
...
```

5 The arched daemon

The arched daemon is the daemon which is used to start every service in WS-ARC. It will load a configuration file, and start the services specified herein.

arched [OPTION...]

(ARC 0.9)

```
-f, --foreground
                             run daemon in foreground
-c, --xml-config
                             full path of XML configuration file
                     path
-i, --ini-config
                     path
                             fill path of INI configuration file
-d, --config-dump
                              dump generated XML configuration
-p, --pid-file
                             full path of PID file
                     path
-u, --user
                      user
                             user name
-g, --group
                             group name
                      group
-s, --schema
                              full path of XML schema file
                     path
-h, --help
                             Show help options
```

If no configuration file is specified, arched first looks for the /etc/arc/server.ini INI configuration file if it does not exist then the /etc/arc/server.xml XML configuration file is tried. If none of these is found arched will abort with an error and exit code 1.

A INI configuration file can be specified with the -i option, while the -c option makes it possible to specify a XML configuration file. If both options are given, the INI configuration will be chosen.

arched also has the capability of printing the XML configuration which will be generated from a given INI configuration. By specifying the -d option along with the -i option and the path to the INI configuration arched will transform the INI configuration to XML and dump the output to standard out and exit.

A List of standard profiles in WS-ARC

A.1 A-REX

Computing Element With Fork MINIMAL configuration template for a secure standalone Computing Element (CE) with a fork queue.

 ${\bf Insecure Computing Element}$

 ${\bf Computing Element With Map file}$

Computing Element With Map file And PBS Backend

 $Computing Element_DN list$

ComputingElement_VOMS

A.2 Chelonia

Chelonia All Centralized A Hash

Chelonia All Centralized A Hash With ISIS

Chelonia All Replicated A Hash

Chelonia All Replicated A Hash Gateway VOMSWith ISIS

Chelonia All Replicated A Hash With ISIS

Chelonia Replicated A Hash

 ${\bf Chelonia Shepherd With Hopi}$

In secure Non Distributed Storage Element

 $NonDistributedStorageElement_DN list$

 $NonDistributedStorageElement_VOMS$

A.3 ISIS

InsecureP2PIIS

InsecureStandaloneIIS

P2PIIS

StandaloneIIS

A.4 Charon

Charon

A.5 Hopi

Hopi

HopiInsecure

 ${\bf HopiWithPlexer}$

 ${\bf HopiWithPlexerInsecure}$

A.6 Combined services

In secure Computing And Storage Element

 $Computing And Storage Element_DN list$

 $Computing And Storage Element_VOMS$

A.7 Testing

Echo

EchoInsecure

EchoPython

 ${\bf EchoPythonInsecure}$

EchoSAMLToken

EchoUsernameToken

EchoX509Token

InsecureHopiService

B Profile attributes naming convention

Since profiles defines a mapping of XML elements or attributes to INI tags, they control the naming of the tags. So for consistency tags in different profiles representing the same XML element or attribute should not be named differently. A naming convention list for the XML elements and attributes described in section 3 is presented below. Note that there are only conventions for leaf XML elements (element with no children).

XML element/attribute	INI tag				
/Server/PidFile	pidfile				
/Server/User	user				
/Server/Group	group				
/Server/Logger/File	logfile				
/Server/Logger/Level	loglevel				
/Server/Logger/Maxsize	logmaxsize				
/Server/Logger/Backups	logbackups				
TCP MCC					
/Component/Listen/Interface	interface				
/Component/Listen/Port	port				
/Component/Listen/Version	ipversion				
/Component/Listen/NoDelay	nodelay				
/Component/Listen/Timeout	timeout				
/Component/Limit	limit				
/Component/Limit.drop	drop				
TLS MCC					
/Component/KeyPath	x509_user_key				
/Component/CertificatePath	x509_user_cert				
/Component/CACertificatePath	x509_cacert_path				
/Component/CACertificatesDir	x509_cacert_dir				
/Component/CACertificatesDir.PolicyGlobus	policyglobus				
/Component/ClientAuthn	clientauthn				
/Component/VOMSCertTrustDNChain/VOMSCertTrustDN					
/Component/VOMSCertTrustDNChain/VOMSCertTrustRegex					
/Component/VOMSCertTrustDNChainsLocation					
/Component/Handshake	handshake				

C XML Schemas

C.1 General Daemon Schema

```
This is the top level element of ARC configuration document.
            </xsd:documentation>
        </xsd:annotation>
        < xsd: sequence >
             <xsd:element ref="Server" minOccurs="0" maxOccurs="1"/>
            <xsd:element ref="loader:ModuleManager" minOccurs="0" maxOccurs="1"</pre>
            <xsd:element ref="loader:Plugins" minOccurs="0" maxOccurs="1"/>
            <xsd:element ref="loader:Component" minOccurs="0" maxOccurs="</pre>
            <xsd:element ref="loader:Chain" minOccurs="0" maxOccurs="unbounded"</pre>
            <xsd:element ref="loader:Plexer" minOccurs="0" maxOccurs="unbounded</pre>
                "/>
            <xsd:element ref="loader:Service" minOccurs="0" maxOccurs="</pre>
                unbounded"/>
            <xsd:element ref="loader:SecHandler" minOccurs="0" maxOccurs="</pre>
                unbounded"/>
        </xsd:sequence>
    </r></rsd:complexType>
</xsd:element>
<!-- Server -->
<xsd:element name="Server">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            Server specific configuration options.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:all>
            <xsd:element name="PidFile" type="xsd:string" minOccurs="0"</pre>
                maxOccurs="1" default="/var/run/arched.pid">
                 <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Path to pid file.
                     </xsd:documentation>
                 </xsd:annotation>
            </xsd:element>
            <xsd:element name="Foreground" type="xsd:boolean" minOccurs="0"</pre>
                maxOccurs="1" default="false">
                 <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Indicates whether the server runs in foreground or daemon
                         mode. If it runs in foreground the log goes to standard
                         error as well.
                     </xsd:documentation>
                 </xsd:annotation>
            </xsd:element>
            <xsd:element name="User" type="xsd:string" minOccurs="0" maxOccurs=</pre>
                "1">
                 <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     arched will run under the specified user. If not specified
                         the effective user will not be changed.
                     </xsd:documentation>
                 </xsd:annotation>
            </r></re></re></re>
            <xsd:element name="Group" type="xsd:string" minOccurs="0" maxOccurs</pre>
                 <xsd:annotation>
                     <xsd:documentation xml:lang="en">
```

```
arched will run under the specified group. If not specified
                         the effective group will not be changed.
                     </xsd:documentation>
                </xsd:annotation>
            </r></r></r>
            <xsd:element ref="Logger" minOccurs="0" maxOccurs="1"/>
        </xsd:all>
    </xsd:complexType>
</xsd:element>
<!-- Logger -->
<xsd:simpleType name="LoggerLevel_Type">
    <xsd:annotation>
        <xsd:documentation xml:lang="en">
        The enumeration lists the supported log levels.
        </xsd:documentation>
    </xsd:annotation>
    <xsd:restriction base="xsd:string">
        <xsd:enumeration value="FATAL"/>
        <xsd:enumeration value="ERROR"/>
        <xsd:enumeration value="WARNING"/>
        <xsd:enumeration value="INFO"/>
        <xsd:enumeration value="VERBOSE"/>
        <xsd:enumeration value="DEBUG"/>
    </xsd:restriction>
</xsd:simpleType>
<xsd:element name="Logger">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            Logger configuration element.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:all>
            <xsd:element name="File" type="xsd:string" minOccurs="0" maxOccurs=</pre>
                "1" default="/var/log/arched.log">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     This element configures the file which should be used for
                        storing log messages.
                     </xsd:documentation>
                </xsd:annotation>
            </r></xsd:element>
            <xsd:element name="Level" type="LoggerLevel_Type" minOccurs="0"</pre>
                maxOccurs="1" default="WARNING">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                    Specifies the log level of the messages which should be
                        logged.
                     </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
            <xsd:element name="Maxsize" type="xsd:nonNegativeInteger" minOccurs</pre>
                ="0" max0ccurs="1">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                    Defines the maximal size of the logfile in bytes.
                     </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
            <xsd:element name="Backups" type="xsd:nonNegativeInteger" minOccurs</pre>
                ="0" max0ccurs="1">
```

C.2 Loader Schema

```
<?xml version="1.0" encoding="UTF-8"?>
< xsd:schema
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    targetNamespace = "http://www.nordugrid.org/schemas/loader/2009/08"
    xmlns="http://www.nordugrid.org/schemas/loader/2009/08"
    xmlns:ini="http://www.nordugrid.org/schemas/ini/2009/08"
    elementFormDefault="qualified"
    attributeFormDefault="unqualified">
<!-- ModuleManager -->
<xsd:element name="ModuleManager">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            This element specifies parameters needed to successfully load
                plugins. Currently it allows to specify filesystem paths to
                directories where plugin libraries are located.
            </xsd:documentation>
        </xsd:annotation>
        < xsd: sequence >
            <xsd:element name="Path" minOccurs="0" maxOccurs="unbounded"</pre>
                default="?">
                <xsd:annotation>
                    <xsd:documentation xml:lang="en">
                    Specify filesystem paths to directories where plugin
                        libraries are located.
                    </xsd:documentation>
                    <xsd:appinfo>
                         <ini:tag>modulepath</ini:tag>
                    </xsd:appinfo>
                </xsd:annotation>
            </xsd:element>
        </xsd:sequence>
    </r></rsd:complexType>
</xsd:element>
<!-- Plugins -->
<xsd:element name="Plugins">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
             This element defines shared library which contains plugins to be
                 used. It is supposed to be used if name of library is not same
                 as name of plugin and hence can't be located automatically.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
```

```
<xsd:element name="Name" minOccurs="0" maxOccurs="unbounded">
                <xsd:annotation>
                    <xsd:documentation xml:lang="en">
                    Specify the name of the plugin.
                    </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
        </xsd:sequence>
    </r></xsd:complexType>
</xsd:element>
<!-- Chain -->
<xsd:element name="Chain">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            This element is not required and does not affect chains directly.
                It's purpose is to group multiple components logically mostly
                for readability purpose.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
            <xsd:element ref="Chain" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:element ref="Component" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:element ref="Plexer" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:element ref="Service" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:element ref="SecHandler" minOccurs="0" maxOccurs="unbounded"/>
        </xsd:sequence>
    </r></re></re>
</xsd:element>
<!-- Component -->
<xsd:element name="next">
    <xsd:complexType>
        <xsd:simpleContent>
            <xsd:extension base="xsd:string">
                <xsd:attribute name="id" type="xsd:string" use="optional"/>
            </xsd:extension>
        </r></xsd:simpleContent>
    </xsd:complexType>
</xsd:element>
<xsd:element name="Component">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            This element defines MCC plugin. Required attribute 'name'
                specifies name of plugin as defined in MCC description. Required
                attribute 'id' assigns identifier which is used to refer to
               this element from others. Sub-elements 'next' refer to next
                components in a chain through their attribute 'id' and their
                content represent assigned component-specific label. If
                attribute 'id' is missing all 'next' refer to next component in
               document. If 'next' is missing one label-less 'next' is assigned
                automatically. Presence of attribute 'entry' exposes this MCC
               through Loader class interface to external code. That is meant
               to be used in code which cretes chains dynamically like client
               utilities. Rest elements define component-specific configuration
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
            <xsd:element ref="next" minOccurs="0" maxOccurs="unbounded"/>
```

```
<xsd:element ref="SecHandler" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:any namespace="##other" processContents="strict" min0ccurs="0"</pre>
                 maxOccurs="unbounded"/>
        </xsd:sequence>
        <xsd:attribute name="name" type="xsd:string" use="required"/>
        <xsd:attribute name="id" type="xsd:string" use="required"/>
        <xsd:attribute name="entry" type="xsd:string" use="optional"/>
        <xsd:anyAttribute namespace="##other" processContents="strict"/>
    </xsd:complexType>
</xsd:element>
<!-- Plexer -->
<xsd:element name="Plexer">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
             This element is a Plexer. Optional attribute 'id' assigns
                 identifier which is used to refer to this element from others.
                 If not specified it will be assigned to "plexer" automatically.
                 Sub-elements 'next' refer to next components in a chain and
                 their content represent requested endpoints. In Plexer content
                 of element 'next' represents Regular Expression pattern. For
                 every incoming message path part of message's endpoint is
                 matched pattern. In case of ordinary service element 'next' may
                 look like
              <next>^/service$</next>
            If service is also responsible for whole subtree then simple
               solution is
              <next>^/service</next>
            But more safer solution would be to use 2 elements
              <next>^/service$</next>
              <next>^/service/</next>
            Unmatched part of message endpoint is propagated with incoming
               message in
            attribute PLEXER: EXTENSION and may be used by service to determine
               response.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
            <xsd:element ref="next" minOccurs="0" maxOccurs="unbounded"/>
            <xsd:any namespace="##other" processContents="strict" minOccurs="0"</pre>
                 maxOccurs="unbounded"/>
        </xsd:sequence>
        <xsd:attribute name="id" type="xsd:string" use="optional"/>
        <xsd:anyAttribute namespace="##other" processContents="strict"/>
    </r></xsd:complexType>
</rsd:element>
<!-- Service -->
<xsd:element name="Service">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
             This element represents a service - last compnent in a chain.
                 Required attribute 'name' specifies name of plugin as defined
                 in Service description. Required attribute 'id' assigns
                 identifier which is used to refer to this element from others.
                 Rest elements define service-specific configuration.
            </xsd:documentation>
        </xsd:annotation>
            <xsd:element ref="SecHandler" minOccurs="0" maxOccurs="unbounded"/>
```

```
<xsd:any namespace="##other" processContents="strict" minOccurs="0"</pre>
                 maxOccurs="unbounded"/>
        </xsd:sequence>
        <xsd:attribute name="name" type="xsd:string" use="required"/>
        <xsd:attribute name="id" type="xsd:string" use="required"/>
        <xsd:anyAttribute namespace="##other" processContents="strict"/>
    </r></xsd:complexType>
</xsd:element>
<!-- SecHandler -->
<xsd:element name="SecHandler">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
             This element specifies security handler plugin to be called at
                 various stages of message processing. Depending on produced
                 result message may be either sent farther through chain or
                 processing would be cancelled. Required attribute 'name'
                 specifies name of plugin. Attibute 'id' creates identifier of
                 SecHandler which may be used to refer to it. If attribute '
                 refid' is defined then configuration of SecHendler is provided
                 by another element within ArcConfig with corresponding 'id'.
                 Attribute 'event' defines to which queue inside MCC SecHandler
                 to be attached. If it's missing SecHandler is attached to
                 default queue if MCC has such. Names of queues are MCC specific
                 . If not otherwise specified they are 'incoming' and 'outgoing'
                 and are processed for incoming and outgoing messages. There is
                 no default queue by default.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
            <xsd:any namespace="##other" processContents="strict" minOccurs="0"</pre>
                maxOccurs="unbounded"/>
        </xsd:sequence>
        <xsd:attribute name="name" type="xsd:string" use="required"/>
        <xsd:attribute name="id" type="xsd:string" use="optional"/>
        <xsd:attribute name="refid" type="xsd:string" use="optional"/>
        <xsd:attribute name="event" type="xsd:string" use="optional"/>
        <xsd:anyAttribute namespace="##other" processContents="strict"/>
    </xsd:complexType>
</xsd:element>
</xsd:schema>
```

C.3 TCP Schema

```
may be multiple Listen elements.
            </xsd:documentation>
        </xsd:annotation>
        < xsd: sequence >
            <xsd:element name="Interface" type="xsd:string" min0ccurs="0"</pre>
                max0ccurs="1" default="0.0.0.0">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Listen network interface.
                     </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
            <xsd:element name="Port" type="xsd:int">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Listen network port.
                     </xsd:documentation>
                 </xsd:annotation>
            </r></re></re></re>
            <xsd:element name="Version" minOccurs="0" maxOccurs="1">
                 <xsd:simpleType>
                     <xsd:annotation>
                         <xsd:documentation xml:lang="en">
                         This element defines TCP/IP protocol version.
                         If not specified both versions will be used whenether
                             possible.
                         </xsd:documentation>
                     </xsd:annotation>
                     <xsd:restriction base="xsd:string">
                         <xsd:enumeration value="4"/>
                         <xsd:enumeration value="6"/>
                     </xsd:restriction>
                </xsd:simpleType>
            </xsd:element>
            <xsd:element name="NoDelay" type="xsd:boolean" minOccurs="0"</pre>
                maxOccurs="1" default="false">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Apply no delay socket option. If set to true TCP packets
                     be proceesd as soon as possible without waiting for more
                     to become available.
                     </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
            <xsd:element name="Timeout" type="xsd:int" minOccurs="0" maxOccurs=</pre>
                "1" default="60">
                <xsd:annotation>
                     <xsd:documentation xml:lang="en">
                     Timeout for socket level operations
                     </xsd:documentation>
                </xsd:annotation>
            </xsd:element>
        </xsd:sequence>
    </xsd:complexType>
</xsd:element>
<! -- Connect -->
<xsd:element name="Connect">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
```

```
This element defines TCP connection to be established to specified
               Host at specified Port. If LocalPort is defined TCP socket will
               be bound to this port number (not supported).
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
            <xsd:element name="Host" type="xsd:string"/>
            <xsd:element name="Port" type="xsd:int"/>
            <xsd:element name="Timeout" type="xsd:int"/>
        </xsd:sequence>
    </xsd:complexType>
</xsd:element>
<xsd:element name="Limit">
    <xsd:complexType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            This element defines upper limit for number of simultaneous
            active TCP connections. Only positive numbers are meaningful.
            If attribute "drop" is specified and is set to true then
            connections over specified limit will be dropped. Otherwise
            they will be put on hold.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:simpleContent>
            <xsd:extension base="xsd:int">
                <xsd:attribute name="drop" type="xsd:boolean" use="optional"/>
            </xsd:extension>
        </xsd:simpleContent>
    </r></rsd:complexType>
</xsd:element>
</xsd:schema>
```

C.4 TLS Schema

```
<?xml version="1.0" encoding="UTF-8"?>
< xsd:schema
    xmlns:xsd="http://www.w3.org/2001/XMLSchema"
    targetNamespace="http://www.nordugrid.org/schemas/tls/2009/08"
    xmlns="http://www.nordugrid.org/schemas/tls/2009/08"
    elementFormDefault="qualified"
    attributeFormDefault="unqualified">
<xsd:element name="KeyPath" type="xsd:string" default="/etc/grid-security/</pre>
   hostkey.pem">
    <xsd:annotation>
        <xsd:documentation xml:lang="en">
        Location of private key.
        Default is /etc/grid-security/hostkey.pem for service
        and $HOME/.globus/userkey.pem for client.
        </xsd:documentation>
    </xsd:annotation>
</xsd:element>
<xsd:element name="CertificatePath" type="xsd:string" default="/etc/grid-</pre>
   security/hostcert.pem">
    <xsd:annotation>
        <xsd:documentation xml:lang="en">
        Location of public certificate.
        Default is /etc/grid-security/hostcert.pem for service and
```

```
$HOME/.globus/usercert.pem for client.
                           </xsd:documentation>
              </xsd:annotation>
</xsd:element>
<xsd:element name="ProxyPath" type="xsd:string">
             <xsd:annotation>
                           <xsd:documentation xml:lang="en">
                           Location of proxy credentials - includes certificates,
                           key and chain of involved certificates. Overwrites
                            elements KeyPath and CertificatePath. Default is /tmp/hash{userid}.0
                                        for client,
                           and none for service.
                            </xsd:documentation>
              </xsd:annotation>
</xsd:element>
<xsd:element name="CACertificatePath" type="xsd:string">
             <xsd:annotation>
                            <xsd:documentation xml:lang="en">
                           Location of certificate of CA. Default is none.
                            </xsd:documentation>
              </xsd:annotation>
</r></re></re></re>
<xsd:element name="CACertificatesDir" default="/etc/grid-security/certificates"</pre>
             <xsd:complexType>
                           <xsd:annotation>
                                         <xsd:documentation xml:lang="en">
                                         Directory containing certificates of accepted CAs.
                                         Default is /etc/grid-security/certificates
                                         </xsd:documentation>
                           </xsd:annotation>
                           <xsd:simpleContent>
                                         <xsd:extension base="xsd:string">
                                                       <xsd:attribute name="PolicyGlobus" type="xsd:boolean" use="</pre>
                                                                   optional" default="false"/>
                                         </xsd:extension>
                           </xsd:simpleContent>
              </r></rsd:complexType>
</xsd:element>
<xsd:element name="ClientAuthn" type="xsd:boolean" default="true">
             <xsd:annotation>
                            <xsd:documentation xml:lang="en">
                               Whether checking client certificate. Only needed for service side.
                           Default is "true"
                            </xsd:documentation>
              </xsd:annotation>
</xsd:element>
<xsd:element name="VOMSCertTrustDNChain">
             <xsd:complexType>
                            <xsd:annotation>
                                         <xsd:documentation xml:lang="en">
                                         The DN list of the trusted voms server credential;
                                         in the AC part of voms proxy certificate, voms proxy % \left( 1\right) =\left( 1\right) \left( 1\right) 
                                         certificate comes with the server certificate which is
                                         used to sign the AC. So when verifying the AC on the
                                         AC-consuming side (in ARC1, it is the MCCTLS which will
                                         consumes the AC), the server certificate will be checked
                                         against a trusted DN list. Only if the DN and issuer's
```

```
DN of server certificate exactly matches the DN list
            in the configuration under TLS component, the AC can be trusted
            </xsd:documentation>
        </xsd:annotation>
        <xsd:sequence>
          <xsd:element name="VOMSCertTrustDN" type="xsd:string" minOccurs="0"</pre>
              maxOccurs="unbounded"/>
          <xsd:element name="VOMSCertTrustRegex" type="xsd:string" min0ccurs</pre>
              ="0"/>
        </xsd:sequence>
    </xsd:complexType>
</r></rsd:element>
<xsd:element name="VOMSCertTrustDNChainsLocation" type="xsd:string">
    <xsd:annotation>
        <xsd:documentation xml:lang="en">
        DN list in an external file, which is in the same format as
            VOMSCertTrustDNChain
        </xsd:documentation>
    </xsd:annotation>
</r></rsd:element>
<xsd:element name="Handshake" default="TLS">
    <xsd:simpleType>
        <xsd:annotation>
            <xsd:documentation xml:lang="en">
            Type of handshake applied. Default is TLS.
            </xsd:documentation>
        </xsd:annotation>
        <xsd:restriction base="xsd:string">
            <xsd:enumeration value="TLS"/>
            <xsd:enumeration value="SSLv3"/>
        </r></xsd:restriction>
    </r></xsd:simpleType>
</r></re></re>
</xsd:schema>
```