SSL tests

SSL testcases are configured in the ssl-tests directory.

Each ssl_*.cnf.in file contains a number of test configurations. These files are used to generate testcases in the OpenSSL CONF format.

The precise test output can be dependent on the library configuration. The test harness generates the output files on the flv.

However, for verification, we also include checked-in configuration outputs corresponding to the default configuration. These testcases live in test/ssl-tests/*.cnf files.

For more details, see ssl-tests/01-simple.cnf.in for an example.

Configuring the test

First, give your test a name. The names do not have to be unique.

An example test input looks like this:

```
name => "test-default",
server => { "CipherString" => "DEFAULT" },
client => { "CipherString" => "DEFAULT" },
test => { "ExpectedResult" => "Success" },
}
```

The test section supports the following options

Test mode

- Method the method to test. One of DTLS or TLS.
- HandshakeMode which handshake flavour to test:
 - Simple plain handshake (default)
 - Resume test resumption
 - RenegotiateServer test server initiated renegotiation
 - RenegotiateClient test client initiated renegotiation

When HandshakeMode is Resume or Renegotiate, the original handshake is expected to succeed. All configured test expectations are verified against the second handshake.

- ApplicationData amount of application data bytes to send (integer, defaults to 256 bytes). Applies to both
 client and server. Application data is sent in 64kB chunks (but limited by MaxFragmentSize and available
 parallelization, see below).

Test expectations

- ExpectedResult expected handshake outcome. One of
 - Success handshake success
 - ServerFail serverside handshake failure
 - ClientFail clientside handshake failure
 - o InternalError some other error
- ExpectedClientAlert, ExpectedServerAlert expected alert. See test/helpers/ssl_test_ctx.c for known values. Note: the expected alert is currently matched against the last received alert (i.e., a fatal alert or a close_notify). Warning alert expectations are not yet supported. (A warning alert will not be correctly matched, if followed by a close notify or another alert.)
- ExpectedProtocol expected negotiated protocol. One of SSLv3, TLSv1, TLSv1.1, TLSv1.2.
- SessionTicketExpected whether or not a session ticket is expected
 - o Ignore do not check for a session ticket (default)
 - Yes a session ticket is expected
 - No a session ticket is not expected
- SessionIdExpected whether or not a session id is expected
 - Ignore do not check for a session id (default)
 - Yes a session id is expected
 - No a session id is not expected
- ResumptionExpected whether or not resumption is expected (Resume mode only)
 - Yes resumed handshake
 - No full handshake (default)
- ExpectedNPNProtocol, ExpectedALPNProtocol NPN and ALPN expectations.
- ExpectedTmpKeyType the expected algorithm or curve of server temp key
- ExpectedServerCertType, ExpectedClientCertType the expected algorithm or curve of server or client certificate
- ExpectedServerSignHash, ExpectedClientSignHash the expected signing hash used by server or client certificate
- ExpectedServerSignType, ExpectedClientSignType the expected signature type used by server or client when signing messages
- ExpectedClientCANames for client auth list of CA names the server must send. If this is "empty" the list is expected to be empty otherwise it is a file of certificates whose subject names form the list.
- ExpectedServerCANames list of CA names the client must send, TLS 1.3 only. If this is "empty" the list is expected to be empty otherwise it is a file of certificates whose subject names form the list.

Configuring the client and server

The client and server configurations can be any valid SSL_CTX configurations. For details, see the manpages for SSL_CONF_cmd .

Give your configurations as a dictionary of CONF commands, e.g.

```
server => {
    "CipherString" => "DEFAULT",
    "MinProtocol" => "TLSv1",
}
```

The following sections may optionally be defined:

- server2 this section configures a secondary context that is selected via the ServerName test option. This context is used whenever a ServerNameCallback is specified. If the server2 section is not present, then the configuration matches server.
- resume_server this section configures the client to resume its session against a different server. This
 context is used whenever HandshakeMode is Resume. If the resume_server section is not present, then the
 configuration matches server.
- resume_client this section configures the client to resume its session with a different configuration. In
 practice this may occur when, for example, upgraded clients reuse sessions persisted on disk. This context is
 used whenever HandshakeMode is Resume. If the resume_client section is not present, then the
 configuration matches client.

Configuring callbacks and additional options

Additional handshake settings can be configured in the extra section of each client and server:

```
client => {
    "CipherString" => "DEFAULT",
    extra => {
        "ServerName" => "server2",
    }
}
```

Supported client-side options

- ClientVerifyCallback the client's custom certificate verify callback. Used to test callback behaviour. One of
 - None no custom callback (default)
 - AcceptAll accepts all certificates.
 - RejectAll rejects all certificates.
- ServerName the server the client should attempt to connect to. One of
 - None do not use SNI (default)
 - o server1 the initial context
 - o server2 the secondary context
 - o invalid an unknown context
- CTValidation Certificate Transparency validation strategy. One of
 - None no validation (default)
 - Permissive SSL_CT_VALIDATION_PERMISSIVE
 - Strict SSL_CT_VALIDATION_STRICT

Supported server-side options

• ServerNameCallback - the SNI switching callback to use

- None no callback (default)
- IgnoreMismatch continue the handshake on SNI mismatch
- RejectMismatch abort the handshake on SNI mismatch
- BrokenSessionTicket a special test case where the session ticket callback does not initialize crypto.
 - No (default)
 - Yes

Mutually supported options

- NPNProtocols, ALPNProtocols NPN and ALPN settings. Server and client protocols can be specified as a comma-separated list, and a callback with the recommended behaviour will be installed automatically.
- SRPUser, SRPPassword SRP settings. For client, this is the SRP user to connect as; for server, this is a known SRP user.

Default server and client configurations

The default server certificate and CA files are added to the configurations automatically. Server certificate verification is requested by default.

You can override these options by redefining them:

```
client => {
    "VerifyCAFile" => "/path/to/custom/file"
}
```

or by deleting them

```
client => {
    "VerifyCAFile" => undef
}
```

Adding a test to the test harness

- 1. Add a new test configuration to test/ssl-tests , following the examples of existing *.cnf.in files (for example, 01-simple.cnf.in).
- 2. Generate the generated *.cnf test input file. You can do so by running generate ssl tests.pl:
 - \$./config \$ cd test \$ TOP=.. perl -l ../util/perl/ generate_ssl_tests.pl ssl-tests/my.cnf.in default > ssl-tests/my.cnf

where my.cnf.in is your test input file and default is the provider to use. For all the pre-generated test files you should use the default provider.

For example, to generate the test cases in ssl-tests/01-simple.cnf.in , do

```
$ TOP=.. perl -I ../util/perl/ generate_ssl_tests.pl \
ssl-tests/01-simple.cnf.in default > ssl-tests/01-simple.cnf
```

Alternatively (hackish but simple), you can comment out

```
unlink glob $tmp_file;
```

in test/recipes/80-test_ssl_new.t and run

```
$ make TESTS=test_ssl_new test
```

This will save the generated output in a *.tmp file in the build directory.

3. Update the number of tests planned in test/recipes/80-test_ssl_new.t. If the test suite has any skip conditions, update those too (see test/recipes/80-test_ssl_new.t for details).

Running the tests with the test harness

```
HARNESS_VERBOSE=yes make TESTS=test_ssl_new test
```

Running a test manually

These steps are only needed during development. End users should run make test or follow the instructions above to run the SSL test suite.

To run an SSL test manually from the command line, the <code>TEST_CERTS_DIR</code> environment variable to point to the location of the certs. E.g., from the root OpenSSL directory, do

```
$ CTLOG_FILE=test/ct/log_list.cnf TEST_CERTS_DIR=test/certs test/ssl_test \
test/ssl-tests/01-simple.cnf default
```

or for shared builds

```
$ CTLOG_FILE=test/ct/log_list.cnf TEST_CERTS_DIR=test/certs \
  util/wrap.pl test/ssl_test test/ssl-tests/01-simple.cnf default
```

In the above examples, default is the provider to use.

Note that the test expectations sometimes depend on the Configure settings. For example, the negotiated protocol depends on the set of available (enabled) protocols: a build with <code>enable-ssl3</code> has different test expectations than a build with <code>no-ssl3</code>.

The Perl test harness automatically generates expected outputs, so users who just run make test do not need any extra steps.

However, when running a test manually, keep in mind that the repository version of the generated tests/*.cnf correspond to expected outputs in with the default Configure options. To run ssl_test manually from the command line in a build with a different configuration, you may need to generate the right *.cnf file from the *.cnf.in input first.