Runtime Configuration

Generally you'll want to use build-time environment variables to provide your configuration. The reason for this is that runtime configuration adds rendering / initialization overhead and is incompatible with Automatic Static Optimization.

To add runtime configuration to your app open next.config.js and add the publicRuntimeConfig and serverRuntimeConfig configs:

```
module.exports = {
    serverRuntimeConfig: {
        // Will only be available on the server side
        mySecret: 'secret',
        secondSecret: process.env.SECOND_SECRET, // Pass through env variables
},
    publicRuntimeConfig: {
        // Will be available on both server and client
        staticFolder: '/static',
     },
}
```

Place any server-only runtime config under serverRuntimeConfig.

Anything accessible to both client and server-side code should be under publicRuntimeConfig.

A page that relies on publicRuntimeConfig must use getInitialProps to opt-out of Automatic Static Optimization. Runtime configuration won't be available to any page (or component in a page) without getInitialProps.

To get access to the runtime configs in your app use next/config, like so:

export default MyImage

Related

Introduction to next.config.js: Learn more about the configuration file used by Next.js.

Environment Variables: Access environment variables in your Next. js application at build time.