Named Tensors

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 1)
Unknown directive type "currentmodule".
... currentmodule:: torch
```

Named Tensors allow users to give explicit names to tensor dimensions. In most cases, operations that take dimension parameters will accept dimension names, avoiding the need to track dimensions by position. In addition, named tensors use names to automatically check that APIs are being used correctly at runtime, providing extra safety. Names can also be used to rearrange dimensions, for example, to support "broadcasting by name" rather than "broadcasting by position".

Warning

The named tensor API is a prototype feature and subject to change.

Creating named tensors

Factory functions now take a new attr: 'names' argument that associates a name with each dimension.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 23); backlink Unknown interpreted text role "attr".

 $Named \ dimensions, \ like \ regular \ Tensor \ dimensions, \ are \ ordered. \ \texttt{tensor.names[i]} \ is \ the \ name \ of \ dimension \ \texttt{i} \ of \ \texttt{tensor.}$

The following factory functions support named tensors:

· :func:`torch.empty`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 37); backlink
Unknown interpreted text role "finc".

• :func:`torch.rand`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 38); backlink
Unknown interpreted text role "func".

• :func:`torch.randn`

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 39); backlink
Unknown interpreted text role "func".

• :func:`torch.ones

System Message: ERROR/3 (b:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 40); backlink
Unknown interpreted text role "func".

• :func:`torch.tensor`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 41); backlink
Unknown interpreted text role "fine".

• :func:`torch.zeros`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 42); backlink
Unknown interpreted text role "func".

Named dimensions

See :attr:`~Tensor.names` for restrictions on tensor names.

 $System\ Message: ERROR/3\ (\texttt{D:}\onboarding-resources}\ sample-onboarding-resources\ pytorch-master]\ [docs]\ [source]\ named_tensor.rst,\ line\ 47); \ \textit{backlink}$

Unknown interpreted text role "attr".

Use :attr: "Tensor.names" to access the dimension names of a tensor and :meth: "Tensor.rename" to rename named dimensions.

 $System\ Message: ERROR/3\ (p:\onboarding-resources\sumple-onboarding-resources\syntheta) resources sumple-onboarding-resources pytorch-master \ docs \ source \ [pytorch-master] \ [docs] \ [source] \ named \ tensor.rst, \ line\ 49); \ backlink$

Unknown interpreted text role "attr".

 $System \ Message: ERROR/3 \ (\ p:\ on boarding-resources \ sample-on boarding-resources \ pytorch-master) \ [docs] \ [source] \ named_tensor.rst, \ line \ 49); \ backlink$

Unknown interpreted text role 'meth'.

```
>>> imgs = torch.randn(1, 2, 2, 3, names=('N', 'C', 'H', 'W'))
>>> imgs.names
('N', 'C', 'H', 'W')
>>> renamed_imgs = imgs.rename(H='height', W='width')
>>> renamed_imgs.names
('N', 'C', 'height', 'width)
```

Named tensors can coexist with unnamed tensors; named tensors are instances of <code>:class:'torch.Tensor'</code>. Unnamed tensors have <code>None-named</code> dimensions. Named tensors do not require all dimensions to be named.

 $System\ Message: ERROR/3\ (p:\onboarding-resources\sumple-onboarding-resources\synthy) to the master \colored by the control of the control$

Unknown interpreted text role "class".

```
>>> imgs = torch.randn(1, 2, 2, 3 , names=(None, 'C', 'H', 'W')) >>> imgs.names (None, 'C', 'H', 'W')
```

Name propagation semantics

Named tensors use names to automatically check that APIs are being called correctly at runtime. This occurs in a process called *name inference*. More formally, name inference consists of the following two steps:

- Check names: an operator may perform automatic checks at runtime that check that certain dimension names must match.
- Propagate names: name inference propagates names to output tensors.

All operations that support named tensors propagate names

```
>>> x = torch.randn(3, 3, names=('N', 'C'))
>>> x.abs().names
('N', 'C')
```

match semantics

Two names *match* if they are equal (string equality) or if at least one is None. Nones are essentially a special "wildcard" name. unify (A, B) determines which of the names A and B to propagate to the outputs. It returns the more *specific* of the two names, if

they match. If the names do not match, then it errors.

Note

In practice, when working with named tensors, one should avoid having unnamed dimensions because their handling can be complicated. It is recommended to lift all unnamed dimensions to be named dimensions by using meth: ~Tensor.refine names`.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 106); backlink
Unknown interpreted text role "meth".
```

Basic name inference rules

Let's see how match and unify are used in name inference in the case of adding two one-dim tensors with no broadcasting.

```
x = torch.randn(3, names=('X',))
y = torch.randn(3)
z = torch.randn(3, names=('Z',))
```

Check names: check that the names of the two tensors match.

For the following examples:

```
>>> # x + y # match('X', None) is True
>>> # x + z # match('X', 'Z') is False
>>> # x + x # match('X', 'X') is True
>>> x + z
Error when attempting to broadcast dims ['X'] and dims ['Z']: dim 'X' and dim 'Z' are at the same position from the right
```

Propagate names: unify the names to select which one to propagate. In the case of x + y, unify('x', None) = 'x' because 'x' is more specific than None.

```
>>> (x + y).names
('X',)
>>> (x + x).names
('X',)
```

For a comprehensive list of name inference rules, see ref" name inference reference-doc. Here are two common operations that may be useful to go over:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 147); backlink
Unknown interpreted text role "ref".
```

• Binary arithmetic ops: ref: unifies_names_from_inputs-doc

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 150); backlink
Unknown interpreted text role "ref".
```

• Matrix multiplication ops: ref contracts_away_dims-doc

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 151); backlink

Unknown interpreted text role "ref".
```

Explicit alignment by names

Use meth:\align_as\ or meth:\align_to\ to align tensor dimensions by name to a specified ordering. This is useful for performing "broadcasting by names".

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 156); backlink
Unknown interpreted text role "meth".
```

 $System\ Message: ERROR/3\ (\texttt{D:\onboarding-resources}\ sample-onboarding-resources\ pytorch-master\ docs\ source\ [pytorch-master]\ [docs]\ [source]\ named_tensor.rst,\ line\ 156); \\ \textit{backlink}$

Unknown interpreted text role "meth".

```
# This function is agnostic to the dimension ordering of `input`,
# as long as it has a `C` dimension somewhere.
def scale_channels(input, scale):
    scale = scale.refine names('C')
    return input * scale.align_as(input)

>>> num_channels = 3
>>> scale = torch.randn(num_channels, names=('C',))
>>> imgs = torch.rand(3, 3, 3, num_channels, names=('N', 'H', 'W', 'C'))
>>> more_imgs = torch.rand(3, num_channels, 3, 3, names=('N', 'C', 'H', 'W'))
>>> videos = torch.randn(3, num_channels, 3, 3, names=('N', 'C', 'H', 'W', 'D')
>>> scale_channels(imgs, scale)
>>> scale_channels(wideos, scale)
```

Manipulating dimensions

Use meth: ~Tensor.align_to` to permute large amounts of dimensions without mentioning all of them as in required by meth: ~Tensor.permute`.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 180); backlink
Unknown interpreted text role "meth".
```

```
System\ Message: ERROR/3\ (\texttt{D:\noboarding-resources}) sample-onboarding-resources \partial partial problems and the problems of the problem
```

Unknown interpreted text role "meth".

```
>>> tensor = torch.randn(2, 2, 2, 2, 2, 2)
>>> named_tensor = tensor.refine_names('A', 'B', 'C', 'D', 'E', 'F')

# Move the F (dim 5) and E dimension (dim 4) to the front while keeping
# the rest in the same order
>>> tensor.permute(5, 4, 0, 1, 2, 3)
>>> named_tensor.align_to('F', 'E', ...)
```

Use "Tensor.flatten" and "meth">"Tensor.unflatten in flatten and unflatten dimensions, respectively. These methods are more verbose than "meth">"Tensor.view" and "meth">"meth">"meth" "Tensor.view" and "meth">"meth" "Tensor.view" and "meth" "Tensor.view" and "meth" "Tensor.view" and "methods is a small respectively. These methods are more verbose than "methods are more verbose than "methods "Tensor.view" and "methods are more view and "methods are view and <a href="metho

```
System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 193); backlink
Unknown interpreted text role "meth".
```

```
System\ Message: ERROR/3\ (\texttt{D:\noboarding-resources}\ \texttt{sample-onboarding-resources}\ \texttt{pytorch-master}\ [\texttt{docs}]\ [\texttt{source}]\ \texttt{named\_tensor.rst},\ \texttt{line}\ 193);\ \textit{backlink}
```

Unknown interpreted text role 'meth'.

 $System\ Message: ERROR/3\ (\texttt{D:}\onboarding-resources}\ sample-onboarding-resources \ pytorch-master\ docs\ source\ [pytorch-master]\ [docs]\ [source]\ named_tensor.rst,\ line\ 193); \\ backlink$

Unknown interpreted text role "meth".

 $System\ Message: ERROR/3\ (p:\onboarding-resources\ sample-onboarding-resources\ pytorch-master\ docs\ source\ [pytorch-master]\ [docs]\ [source]\ named_tensor.rst,\ line\ 193); \\ \textit{backlink}$

Unknown interpreted text role "meth".

Autograd support

Autograd currently supports named tensors in a limited manner; autograd ignores names on all tensors. Gradient computation is still correct but we lose the safety that names give us.

```
>>> x = torch.randn(3, names=('D',))
>>> weight = torch.randn(3, names=('D',), requires_grad=True)
>>> loss = (x - weight).abs()
>>> grad_loss = torch.randn(3)
>>> loss.backward(grad_loss)
>>> weight.grad # Unnamed for now. Will be named in the future
tensor([-1.8107, -0.6357, 0.0783])
>>> weight.grad.zero_()
>>> grad_loss = grad_loss.refine_names('C')
>>> loss.backward(grad_loss)
>>> weight.grad.zero_()
# Ideally we'd check that the names of loss and grad_loss match but we don't yet.
>>> loss.backward(grad_loss)
>>> weight.grad
tensor([-1.8107, -0.6357, 0.0783])
```

Currently supported operations and subsystems

Operators

See ref'name_inference_reference-doc' for a full list of the supported torch and tensor operations. We do not yet support the following that is not covered by the link:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 244); backlink
Unknown interpreted text role "ref".
```

· indexing, advanced indexing.

For torch.nn.functional operators, we support the following:

• :func:`torch.nn.functional.relu`

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 251); backlink
Unknown interpreted text role "func".
```

• :func:`torch.nn.functional.softmax`

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 252); backlink
Unknown interpreted text role "fine".
```

• :func:`torch.nn.functional.log_softmax`

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 253); backlink

Unknown interpreted text role "fime".
```

• :func:`torch.nn.functional.tanh`

```
System Message: ERROR/3 (b:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 254); backlink

Unknown interpreted text role "func".
```

• :func:`torch.nn.functional.sigmoid

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 255); backlink
Unknown interpreted text role "func".

• :func:`torch.nn.functional.dropout`

System Message: ERROR/3 (b:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 256); backlink
Unknown interpreted text role "func".

Subsystems

Autograd is supported, see ref: named_tensors_autograd-doc. Because gradients are currently unnamed, optimizers may work but are untested.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 261); backlink
Unknown interpreted text role "ref".

NN modules are currently unsupported. This can lead to the following when calling modules with named tensor inputs:

- NN module parameters are unnamed, so outputs may be partially named.
- NN module forward passes have code that don't support named tensors and will error out appropriately.

We also do not support the following subsystems, though some may work out of the box:

- distributions
- serialization (:func:'torch.load', :func:'torch.save')

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 275); backlink
Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 275); backlink
Unknown interpreted text role "finc".

- multiprocessing
- JIT
- distributed
- ONNX

If any of these would help your use case, please search if an issue has already been filed and if not, file one.

Named tensor API reference

In this section please find the documentation for named tensor specific APIs. For a comprehensive reference for how names are propagated through other PyTorch operators, see reff name inference_reference-doc'.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 288); backlink
Unknown interpreted text role 'ref'.

System Message: ERROR/3 (p:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 295)

Unknown directive type "autoattribute".

.. autoattribute:: names

 $System\ Message: ERROR/3\ (\texttt{D:\onboarding-resources}\ sample-onboarding-resources\ pytorch-master\ [docs]\ [source]\ named_tensor.rst,\ line\ 296)$

Unknown directive type "automethod".

.. automethod:: rename

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 297)

Unknown directive type "automethod".

.. automethod:: rename_

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 298)

```
Unknown directive type "automethod".

... automethod:: refine_names

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source] named_tensor.rst, line 300)

Unknown directive type "automethod".
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\pytorch-master\docs\source\[pytorch-master] [docs] [source]named_tensor.rst, line 301)
Unknown directive type "automethod".

.. automethod:: align_to

.. automethod:: align_as

 $System\,Message: ERROR/3~(\texttt{D:\onboarding-resources}) sample-onboarding-resources \end{array} to character $$ docs \simeq [pytorch-master] [docs] [source] named_tensor.rst, line 303) $$$

Unknown directive type "automethod".

.. automethod:: unflatten

 $System\ Message: ERROR/3\ (\texttt{D:\onboarding-resources}\ sample-onboarding-resources\ pytorch-master\ [docs]\ [source]\ named_tensor.rst,\ line\ 304)$

Unknown directive type "py:method".

```
.. py:method:: flatten(dims, out_dim) -> Tensor
    :noindex:

Flattens :attr:`dims` into a single dimension with name :attr:`out_dim`.

All of `dims` must be consecutive in order in the :attr:`self` tensor,
but not necessary contiguous in memory.

Examples::

>>> imgs = torch.randn(32, 3, 128, 128, names=('N', 'C', 'H', 'W'))
>>> flat_imgs = imgs.flatten(['C', 'H', 'W'], 'features')
>>> flat_imgs.names, flat_imgs.shape
    (('N', 'features'), torch.Size([32, 49152]))

.. warning:
    The named tensor API is experimental and subject to change.
```