ioctl VIDIOC CREATE BUFS

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-api][media][v41]vidioc-create-bufs.rst, line 2)
Unknown directive type "cnamespace".
```

.. c:namespace:: V4L

Name

VIDIOC CREATE BUFS - Create buffers for Memory Mapped or User Pointer or DMA Buffer I/O

Synopsis

```
System\ Message: ERROR/3\ (\cite{Continue}) in which is a master \cite{Continue} and the continue of the con
```

Unknown directive type "c:macro".

```
.. c:macro:: VIDIOC_CREATE_BUFS
```

int ioctl(int fd, VIDIOC CREATE BUFS, struct v412 create buffers *argp)

Arguments

fd

File descriptor returned by :c:func:'open()'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 26); backlink

Unknown interpreted text role "c:func".

argp

Pointer to struct :c:type:\v412 create buffers\`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 29); backlink

Unknown interpreted text role "c:type".

Description

This ioctl is used to create buffers for ref. memory mapped mmap> or ref. user pointer <userp> or ref. DMA buffer <</pre>
I/O. It can be used as an alternative or in addition to the ref. VIDIOC_REQBUFS ioctl, when a tighter control over buffers is required. This ioctl can be called multiple times to create buffers of different sizes.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41]vidioc-create-bufs.rst, line 34); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 34); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 34); backlink

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 34); backlink

Unknown interpreted text role 'ref'.

To allocate the device buffers applications must initialize the relevant fields of the struct <code>:c:type:`v412_create_buffers`</code> structure. The count field must be set to the number of requested buffers, the <code>memory</code> field specifies the requested I/O method and the <code>reserved</code> array must be zeroed.

 $System\ Message: ERROR/3\ (\texttt{D:\noboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master\]\ [Documentation\]\ [userspace-api\]\ [media\]\ [v41\]\vidioc-create-bufs.rst, line\ 41); \\ backlink$

Unknown interpreted text role "c:type".

The format field specifies the image format that the buffers must be able to handle. The application has to fill in this struct <code>c:type:'v4l2_format'</code>. Usually this will be done using the <code>ref:'VIDIOC_TRY_FMT < VIDIOC_G_FMT>'</code> or <code>ref:'VIDIOC_G_FMT < VIDIOC_G_FMT>'</code> ioctls to ensure that the requested format is supported by the driver. Based on the format's <code>type</code> field the requested buffer size (for single-planar) or plane sizes (for multi-planar formats) will be used for the allocated buffers. The driver may return an error if the size(s) are not supported by the hardware (usually because they are too small).

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 47); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 47); backlink

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 47); backlink

Unknown interpreted text role "ref".

The buffers created by this ioctl will have as minimum size the size defined by the <code>format.pix.sizeimage</code> field (or the corresponding fields for other format types). Usually if the <code>format.pix.sizeimage</code> field is less than the minimum required for the given format, then an error will be returned since drivers will typically not allow this. If it is larger, then the value will be used as-is. In other words, the driver may reject the requested size, but if it is accepted the driver will use it unchanged.

When the ioctl is called with a pointer to this structure the driver will attempt to allocate up to the requested number of buffers and store the actual number allocated and the starting index in the count and the index fields respectively. On return count can be smaller than the number requested.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 73)

Unknown directive type "c:type".

```
.. c:type:: v4l2_create_buffers
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\Documentation\userspace-api\media\v41\[linux-master][Documentation][userspace-
api][media][v41]vidioc-create-bufs.rst, line 75)

Unknown directive type "tabularcolumns".

.. tabularcolumns:: |p{4.4cm}|p{4.4cm}|p{8.5cm}|
```

```
System\,Message:\,ERROR/3\,(\texttt{D:}\nonline) - resources \verb|\sample-onboarding-resources|| the control of the contr
master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-
api] [media] [v41] vidioc-create-bufs.rst, line 77)
Unknown directive type "flat-table".
         .. flat-table:: struct v412 create buffers
                  :header-rows: 0
                  :stub-columns: 0
                  :widths:
                                                    1 1 2
                                u32
                      - ``index``
                       - The starting buffer index, returned by the driver.
                  * - _u32
- ``count``
                       - The number of buffers requested or granted. If count == 0, then
                            :ref:`VIDIOC CREATE BUFS` will set ``index`` to the current number of
                            created buffers, and it will check the validity of ``memory``
                           ``format.type``. If those are invalid -1 is returned and errno is set to ``EINVAL`` error code, otherwise :ref:`VIDIOC_CREATE_BUFS` returns 0. It will never set errno to ``EBUSY`` error code in this particular
                           case.
                       - _u32
- ``memory``
                      - Applications set this field to ``V4L2_MEMORY MMAP``,
                                `V4L2 MEMORY DMABUF`` or ``V4L2 MEMORY USERPTR``. See
                           :c:type:`v412_memory`
                  * - struct :c:type:`v412_format`
                      - ``format``
                       - Filled in by the application, preserved by the driver.
                  * - _u32
- ``capabilities``
                       - Set by the driver. If 0, then the driver doesn't support
                           capabilities. In that case all you know is that the driver is
                            guaranteed to support ``V4L2_MEMORY_MMAP`` and *might* support
                           other :c:type:`v412 memory` types. It will not support any other
                           capabilities. See :ref:`here <v4l2-buf-capabilities>` for a list of the
                           capabilities.
                           If you want to just query the capabilities without making any other changes, then set ``count`` to 0, ``memory`` to ``V4L2\_MEMORY\_MMAP`` and ``format.type`` to the buffer type.
                       - __u32
- ``flags``
                       - Specifies additional buffer management attributes.
                           See :ref:`memory-flags`.
                                u32
                      - ``reserved``\ [6]
                       - A place holder for future extensions. Drivers and applications
                           must set the array to zero.
```

Return Value

On success 0 is returned, on error -1 and the errno variable is set appropriately. The generic error codes are described at the ref. Generic Error Codes <gen-errors>` chapter.

```
System\ Message: ERROR/3\ (\texttt{D:\noboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master\] [Documentation\] [userspace-api\] [media\] [v41] vidioc-create-bufs.rst, line 128); backlink
```

Unknown interpreted text role 'ref'.

No memory to allocate buffers for ref:'memory mapped <mmap>' I/O.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\[linux-master] [Documentation] [userspace-api] [media] [v41] vidioc-create-bufs.rst, line 133); backlink Unknown interpreted text role "ref".

EINVAL

The buffer type (format.type field), requested I/O method (memory) or format (format field) is not valid.