

# Chapter 18 - The AHX Engine

AHX is a four-voice chip-tune music engine. It plays AHX module data from memory and generates synthetic square, saw, envelope, vibrato, and effect changes without sample data. The reader-facing path is simple: put AHX data in memory, set pointer and length, start playback, and poll status.

```
10 REM AHX MEMORY PLAYBACK
20 POKE &H000F0800,1
30 REM START SUBSONG 0 FROM MEMORY
40 AHX PLAY &H00100000,&H00004000,0
50 PRINT AHX STATUS
```

If valid AHX data is present at \$00100000, playback starts and AHX STATUS reports the busy bit.

Line 40 writes the pointer, length, subsong, and start command. Line 50 reads the status register once; it does not stop the tune.

## 18.1 Shape of the engine

| Item      | Value                                          |
|-----------|------------------------------------------------|
| Voices    | 4                                              |
| Data      | AHX or THX module data in memory               |
| Subsongs  | Selected by AHX_SUBSONG                        |
| Output    | Mixed into the global audio output             |
| Plus mode | Enhanced AHX processing at AHX_PLUS_CTRL bit 0 |
| Status    | Busy and error bits in AHX_PLAY_STATUS         |

AHX is a playback engine, not a register-level tone chip like SID or POKEY. There are no per-note BASIC commands in this chapter. Use the player registers or the AHX PLAY keyword.

## 18.2 Register block

| Address | Name            | Purpose                             |
|---------|-----------------|-------------------------------------|
| \$F0B80 | AHX_PLUS_CTRL   | Bit 0 enables AHX Plus              |
| \$F0B84 | AHX_PLAY_PTR    | Start address of AHX data           |
| \$F0B88 | AHX_PLAY_LEN    | Length in bytes                     |
| \$F0B8C | AHX_PLAY_CTRL   | Write 1 start, 2 stop, 5 start loop |
| \$F0B90 | AHX_PLAY_STATUS | Bit 0 busy, bit 1 error             |
| \$F0B91 | AHX_SUBSONG     | Subsong number                      |

AHX\_PLAY\_PTR, AHX\_PLAY\_LEN, and AHX\_PLAY\_CTRL are 32-bit registers. AHX\_SUBSONG is a byte. AHX\_PLUS\_CTRL can be read back as 0 or 1.

## 18.3 BASIC keywords

| Form                        | Effect                                |
|-----------------------------|---------------------------------------|
| AHX PLAY addr, len          | Start playback from memory            |
| AHX PLAY addr, len, subsong | Select a subsong, then start playback |
| AHX STOP                    | Stop playback                         |
| AHX PLUS ON                 | Enable AHX Plus processing            |
| AHX PLUS OFF                | Disable AHX Plus processing           |
| AHX STATUS                  | Expression reading AHX_PLAY_STATUS    |

The equivalent raw register setup is:

```
10 REM AHX RAW START
20 POKE &H000F0800,1
30 REM POINTER, LENGTH, SUBSONG
40 POKE &H000F0B84,&H00100000
50 POKE &H000F0B88,&H00004000
60 POKE8 &H000F0B91,0
70 REM START, THEN READ STATUS
80 POKE &H000F0B8C,1
90 PRINT PEEK8(&H000F0B90)
```

Expected result: line 80 starts the player. Line 90 prints a status byte whose low bit is set while the player is busy, or bit 1 if the data cannot be read or parsed.

The raw form shows what AHX PLAY does for you. The pointer and length are 32-bit registers, the subsong is a byte register, and the control register starts playback when written with 1.

## 18.4 AHX Plus

AHX Plus follows the shared Plus rule from Chapter 11. AHX PLUS ON writes 1 to AHX\_PLUS\_CTRL at \$F0B80; AHX PLUS OFF writes 0. The AHX data and player registers stay the same. The AHX-specific difference is four-voice gain, stereo spread, oversampling, low-pass smoothing, drive, and room processing.

```

10 REM AHX PLUS TOGGLE
20 POKE &H000F0800,1
30 AHX PLAY &H00100000,&H00004000,0
40 REM LISTEN TO STANDARD AHX FIRST
50 FOR T=1 TO 3000
60 NEXT T
70 AHX PLUS ON
80 PRINT PEEK8(&H000F0B80)
90 REM NOW LISTEN TO AHX PLUS
100 FOR T=1 TO 3000
110 NEXT T
120 AHX PLUS OFF
130 PRINT PEEK8(&H000F0B80)

```

Expected result: line 80 prints 1; line 130 prints 0.

The song data and playback registers do not change when Plus is toggled. Only the output processing path changes, so playback continues while the two status prints confirm the control value.

## 18.5 Status and errors

AHX\_PLAY\_STATUS and AHX STATUS use these bits:

| Bit | Meaning         |
|-----|-----------------|
| 0   | Busy or playing |
| 1   | Error           |

The player sets the error bit if the memory pointer is not readable, the length is zero, the length is larger than the AHX limit, the address range wraps, or the data is not a valid AHX module.

```

10 REM AHX STATUS CHECK
20 REM START WITHOUT STOPPING IMMEDIATELY
30 AHX PLAY &H00100000,&H00004000,0
40 S=AHX STATUS
50 PRINT S
60 IF S AND 2 THEN PRINT "AHX ERROR"
70 IF S AND 1 THEN PRINT "AHX BUSY"

```

Line 40 samples the status register after the start command. Lines 60 and 70 decode the two useful bits. A good example should not call AHX STOP here, because that would prove only that stop works.

To stop playback later:

```

10 AHX STOP
20 PRINT AHX STATUS

```

## 18.6 Limits

The AHX player reads the module data from memory when playback starts. Changing the memory block after AHX PLAY does not change the already loaded song. AHX\_SUBSONG is an eight-bit value. AHX STOP writes control value 2 and clears the busy state.

For loading named music files from BASIC, use the media loader in Chapter 23.

The next chapter covers MOD playback, the sample-based four-channel music path.