Министерство образования Республики Беларусь

Учреждение образования БЕЛОРУССКИЙ ГОСУДАРСТВЕННЫЙ УНИВЕРСИТЕТ ИНФОРМАТИКИ И РАДИОЭЛЕКТРОНИКИ

Факультет компьютерных систем и сетей

Кафедра электронных вычислительных машин


Дисциплина: Администрирование компьютерных систем и сетей

ОТЧЁТ к лабораторной работе № 2

 Студент:
 И. В. Григорик

 Проверил:
 В. А. Марцинкевич

1. Реализация топологии в Cisco Packet Tracer.



2.1. Расчёт масок подсетей.

Подсети записываются в формате A.B.C.D/S, где S — размер в маски подсети битах. Для быстрого получения масок используем следующий метод:

- 1. Поделить размер маски на 8, в количестве целой части от деления записать элементы «255».
- 2. Если остаток есть, следующий элемент считаем по формуле:


$$\sum_{k=1}^{n} 2^{8-k}$$
, где n – остаток от деления.

3. Если маска ещё не из четырёх элементов, заполняем следующие элементы нулями. Таким образом:

Номер	Подсеть	Маска
1	6.0.0.0/10	255.192.0.0
2	61.32.0.0/11	255.224.0.0
3	95.22.68.0/26	255.255.255.192
4	123.32.0.0/12	255.240.0.0
5	131.118.0.0/16	255.255.0.0
6	154.7.160.0/20	255.255.240.0
7	169.2.204.0/24	255.255.255.0
8	191.197.95.96/29	255.255.255.248
9	199.107.70.120/29	255.255.255.248

2.2. Расчёт первого и последнего адреса для подсети № 1.

Представим подсеть (6.0.0.0/10)» в битовом виде, отметим биты маски серыми слетками:



Нельзя изменять биты маски, зная это запишем первый и последний адрес в этой подсети. Первый адрес:

6	0	0	1		
0 0 0 0 0 1 1 0	0 0 0 0 0 0 0 0	0 0 0 0 0 0 0 0	0 0 0 0 0 0 0 1		

В последнем адресе все биты узла, кроме последнего, будут установлены в «1», так как адрес со всеми битами узла, установленными в «1», будет считаться широковещательным, то есть отправка по нему будет означать отправку пакеты всем узлам в данной подсети.

6	6 63		254		
0 0 0 0 0 1 1 0	0 0 1 1 1 1 1 1	1 1 1 1 1 1 1 1	1 1 1 1 1 1 1 0		

3. Конфигурации.

T	•	
1.0		

Router>show ip int br Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	6.0.0.1	YES	manual	up	up
FastEthernet0/1	95.22.68.1	YES	manual	up	up
FastEthernet1/0	61.63.255.254	YES	manual	up	up
Vlan1	unassigned	YES	unset	administratively down	down
N2. Router>show ip interfac	ce brief				
Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	61.32.0.1	YES	manual	up	up
FastEthernet0/1	196.168.0.2	YES	manual	up	up
FastEthernet1/0	unassigned	YES	unset	administratively down	down
Vlanl	unassigned	YES	unset	administratively down	down

N3. Router>sh ip int br				
Interface	IP-Address	OK? Method	Status	Protocol
FastEthernet0/0	unassigned	YES unset	administratively down	down
FastEthernet0/1	unassigned	YES unset	administratively down	down
FastEthernet1/0	unassigned	YES unset	administratively down	down
Vlanl	unassigned	YES unset	administratively down	down
N4 Router>sh ip int br Interface	IP-Address	OK? Method	Status	Protocol
FastEthernet0/0	131.118.255.254	YES manual	up	up
FastEthernet0/1	154.7.160.1	YES manual	up	up
FastEthernet1/0	unassigned	YES unset	administratively down	down
Vlanl	unassigned	YES unset	administratively down	down
N5 sh ip int br Interface	IP-Address	OK? Method	Status	Protocol
FastEthernet0/0	192.168.1.2	YES manual	up	up
FastEthernet0/1	unassigned	YES unset	administratively down	down
FastEthernet0/1 FastEthernet1/0	unassigned 191.197.95.102		_	down
	191.197.95.102	YES manual	_	up
FastEthernet1/0	191.197.95.102	YES manual	up	up
FastEthernet1/0	191.197.95.102	YES manual	up administratively down	up
FastEthernet1/0 Vlan1 N6 Router>sh ip int br	191.197.95.102 unassigned	YES manual YES unset OK? Method	up administratively down Status	up down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface	191.197.95.102 unassigned IP-Address	YES manual YES unset OK? Method	up administratively down Status up	up down Protocol
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1	YES manual YES unset OK? Method YES manual YES manual	up administratively down Status up	up down Protocol up up
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned	YES manual YES unset OK? Method YES manual YES manual YES unset	up administratively down Status up up	up down Protocol up up down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1 FastEthernet1/0	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned	YES manual YES unset OK? Method YES manual YES manual YES unset	up administratively down Status up up administratively down	up down Protocol up up down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1 FastEthernet1/0 Vlan1	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned unassigned unassigned	YES manual YES unset OK? Method YES manual YES manual YES unset	up administratively down Status up up administratively down administratively down	up down Protocol up up down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1 FastEthernet1/0 Vlan1 N7 Router>sh ip int br	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned unassigned unassigned	YES manual YES unset OK? Method YES manual YES manual YES unset YES unset	up administratively down Status up up administratively down administratively down	up down Protocol up up down down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1 FastEthernet1/0 Vlan1 N7 Router>sh ip int br Interface	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned unassigned unassigned	YES manual YES unset OK? Method YES manual YES manual YES unset YES unset OK? Method YES manual	up administratively down Status up up administratively down administratively down Status up	up down Protocol up up down down
FastEthernet1/0 Vlan1 N6 Router>sh ip int br Interface FastEthernet0/0 FastEthernet0/1 FastEthernet1/0 Vlan1 N7 Router>sh ip int br Interface FastEthernet0/0	191.197.95.102 unassigned IP-Address 123.47.255.254 169.2.204.1 unassigned unassigned IP-Address 154.7.175.254	YES manual YES unset OK? Method YES manual YES manual YES unset YES unset OK? Method YES manual	up administratively down Status up up administratively down administratively down Status up up	up down Protocol up down down Protocol up

N8 Router>sh ip int br					
Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	6.63.255.254	YES	manual	up	up
FastEthernet0/1	199.107.70.121	YES	manual	up	up
FastEthernet1/0	131.118.0.1	YES	manual	up	up
Vlanl	unassigned	YES	unset	administratively down	down

4. Последовательность действий в Windows.

Порядок действий полученный на Windows 11:

- 1. Нажать кнопку «Пуск»
- 2. Нажать на кнопку «settings».
- 3. Перейти в раздел «Network & Internet»
- 4. Под своим подключением нажать кнопку «Properties»
- 5. Нажать кнопку «Edit» в поле «IP Settings»
- 6. Переключить режим из «automatic» в «manual»
- 7. Включить IPv4
- 8. Настроить сеть
- 9. Подтвердить изменения нажав «ОК» в двух последних окнах.



Установленный последний адрес из подсети № 1.

```
Адаптер Ethernet Ethernet:

DNS-суффикс подключения . . . :
Локальный IPv6-адрес канала . . : fe80::d1b3:61e0:a546:1bec%7
IPv4-адрес . . . . . . . : 14.202.128.1
Маска подсети . . . . . : 255.255.192.0
Основной шлюз . . . . : 14.202.128.2

C:\Users\DIMA_PC>ipconfig
```

Подтверждение установки адреса через команду «ipconfig».

5. Последовательность действий в Linux.

Необходимый файл находится по пути: «/etc/netctl/enp1s0». Содержание файла:

«Description='A basic static ethernet connection'

Interface=enp1s0

Connection=ethernet

IP=static

Address=('192.168.31.1)

Gateway=('192.168.31.2')

DNS=('8.8.8.8')»