


Step 1 — Download Tailscale


Open <https://tailscale.com/download> in your browser. Pick the **Windows** tab, click **Download Tailscale for Windows**, run the installer, and click **Close** when it finishes.



Sign in to GitHub first if you are not already signed in — Tailscale will need it in step 3.

Step 2 — Tailscale first-run sign-in


Click the Tailscale icon in the system tray. The dialog **"To install Tailscale, you must first sign in"** appears. Click **Sign in** — your browser will open to the Tailscale login page. (If the browser does not open, click **Copy link** and paste the URL manually.)



Leave this dialog open while you sign in. It will close on its own when the browser sign-in completes.

Step 3 — Sign in with GitHub


On the Tailscale login page, click **Sign in with GitHub**. Use the PacGate GitHub account (look up the email and password in `OPERATOR.md`). Approve the Tailscale OAuth app on GitHub. When the browser tab finishes, the Tailscale tray icon turns green — you are in the tailnet.



Done with Tailscale. Next: install RustDesk.

Step 4 — Download RustDesk


Open <https://rustdesk.com/download> in your browser. Make sure the **Windows** tab and **Windows 64bit (Installer)** are selected. Click the **Github** button (not the fast mirror) and run the installer. Leave **"Install RustDesk as a service"** checked and click **Finish**.



The RustDesk **ID** shown in the main window is what the remote operator will use to connect. Write it down in `OPERATOR.md`.

Step 5 — RustDesk network settings


In RustDesk, click **⋮** → **Settings** → **Network**. Keep the defaults: **ID Server** = `rs-nj.rustdesk.com`, **Key** = `new`, **Relay Server** = `empty`, **Use my own ID server** = `unchecked`. Click **Apply** → **OK**.



No need to touch any ports — RustDesk connects outbound. The remote operator reaches you over the Tailscale tailnet.

Step 6 — Set a permanent password


Still in RustDesk **Settings**, find **Set permanent password**. Type a strong password (16+ characters, mix of letters/numbers/symbols) and click **Save**. Save the password in your password manager — anyone with your RustDesk **ID** and this password can connect to this machine unattended.



Do not reuse your Windows or GitHub password. **Do not** share the permanent password over chat — use a password manager shared vault.

Step 7 — Confirm port 21118 is open

Press **Win + R**, type `services.msc`, press **Enter**. Find the `rustdesk` service. **Status = Running**, **Startup Type = Automatic**. RustDesk uses **port 21118** — that is the only port the remote operator needs.



🎉 Done. Hand the RustDesk **ID** to the PacGate admin and they can connect through the tailnet on port 21118.