

Vaultly Installation Guide

Version: 2.4.1

Last Updated: March 12, 2025

System Requirements

Before installing Vaultly, ensure your system meets the following minimum requirements:

- * Operating System: Ubuntu 20.04+, Debian 11+, macOS 12+, or Windows 10 (64-bit)
- * Python: Python 3.10 or higher
- * RAM: Minimum 2 GB (4 GB recommended for production)
- * Disk Space: Minimum 10 GB free disk space
- * Network: Outbound HTTPS (port 443) access required for license validation

Vaultly will not start on Python versions below 3.10 due to use of structural pattern matching and required standard library features introduced in that version.

Installation Steps

Step 1 - Install via pip

Vaultly is distributed as a standard Python package. Install the latest stable release with:

```
pip install vaultly==2.4.1
```

To install a specific earlier version, replace 2.4.1 with your target version number.

Step 2 - Initialize configuration

After installation, generate the default configuration file by running:

```
vaultly init
```

This creates the configuration file at `/etc/vaultly/config.yaml`. On Windows, the equivalent path is `C:\ProgramData\Vaultly\config.yaml`. Review this file and set your database connection string, storage backend, and secret key before proceeding.

Step 3 - Set environment variables

Vaultly reads sensitive credentials from environment variables. At minimum, set:

```
export VAULTLY_SECRET_KEY="your-secret-key-here"
export VAULTLY_DB_URL="postgresql://user:password@localhost:5432/vaultly"
```

Step 4 - Start the server

Launch the Vaultly server with:

```
vaultly start --port 8080
```

The default port is 8080. Pass `--port <number>` to use a different port. The server binds to 0.0.0.0 by default; use `--host 127.0.0.1` to restrict to localhost only.

Step 5 - Verify the installation

Once the server is running, open your browser and navigate to <http://localhost:8080/health>. A successful response looks like:

```
{ "status": "ok", "version": "2.4.1" }
```

Upgrading from a Previous Version

To upgrade an existing Vaultly installation, run:

```
pip install --upgrade vaultly
vaultly db migrate
vaultly start --port 8080
```

Always run `vaultly db migrate` after upgrading to apply any pending database schema changes. Skipping this step may cause runtime errors.

Uninstalling Vaultly

To completely remove Vaultly:

```
pip uninstall vaultly
rm -rf /etc/vaultly
rm -rf /var/log/vaultly
```

This removes the application, configuration, and logs. Your database and uploaded documents stored in external storage are not deleted by this process.

Getting Help

If the installation fails, consult the [Troubleshooting Guide](#) or contact support@vaultly.io.