EGYSZERŰ AUTOCAD DXF FÁJL SZERKEZETE

FÁJL STRUKTÚRA

A DXF az AutoCAD egy sima ASCII szöveges állománya, meghatározott szerkezet szerint felépítve, ahol két egymást követő sor mindig összetartozik, az első sor egy típuskódot ad meg, a második az adott típushoz/elemhez tartozó értéket.

Alap felépítés:

A DXF fájl különböző szekciókból állhat, de ebből csak az ENTITIES kötelező, utána egy fájl vége jel van (EOF – end of file).

- 1. HEADER szekció Fejléc. Általános információk, változók opcionális
- 2. CLASSES szekció opcionális
- 3. TABLES szekció Különböző definíciók opcionális
 - a. Linetype table (LTYPE)
 - b. Layer table (LAYER) itt lehetne rétegeket definiálni, de új réteget az entitás szekción belül is létre lehet hozni, csak a réteg kóddal (8) és a réteg név megadásával, alap beállításokkal
 - c. Text Style table (STYLE)
 - d. View table (VIEW)
 - e. User Coordinate System table (UCS)
 - f. Viewport configuration table (VPORT)
 - g. Dimension Style table (DIMSTYLE)
 - h. Application Identification table (APPID)
- 4. BLOCKS szekció Blokk definíciók opcionális (ha nincs blokk a fájlban, akkor nem kell)
- 5. ENTITIES section Rajzi elemek (pontok, vonalak stb.) KÖTELEZŐ!
- 6. OBJECTS szekció opcionális

Szekciók előtt meg kell adni, hogy most egy új szekció jön (0 kód, SECTION), majd utána a szekció nevét (2-es kód, név). Majd a tartalom után jön a szekció vége (0 kód, ENDSEC), legvégül fájl vége jel (0 kód, EOF). Pl.

0 SECTION 2 ENTITIES ... 0 ENDSEC ... 0

EOF

További kódokat lásd az 1. táblázatban a szöveg után, néhány gyakran használt kódot vastaggal kiemelve. Néhány rajzi elem leírását az ENTITIES szekción belül lásd a 2. táblázatban. Egyszerű példák DXF fájlra:

PONT MEGADÁSA DXF FÁJLBAN

A következő példa egy pont rajzol a 35.23, 12.89 koordinátákhoz.

Simple point.dxf:

0 SECTION	Szekció eleje
2 ENTITIES	Rajzi elemek szekció követezik
0 POINT	Pont típusú elem
8 pontok 10 35.23 20 12.89 0 ENDSEC 0 EOF	Rétegmegadás kódja 'pontok' a réteg neve X koordináta Y koordináta Szekció vége Fájl vége

A fenti fájl egy pontot tesz le, de a pont stílusa az alap beállításként használt pici pötty, ha ezt meg akarjuk változtatni, akkor kell a HEADER szekció is, és be kell állítani a pont stílusát a PDMODE változóban. PDMODE értéke lehet pl. 2 (+), 3 (X), 34 (⊕). Ehhez az előbbi előtt a HEADER szekciót is definiálni kell.

0 SECTION	Szekció eleje
2	Fejléc szekció követezik
HEADER	,
9	Változó definiálás jön
\$PDMODE	PDMODE változó
70	Változó értékadása (egész típusú)
34	értéke: 34 (⊕)
0	Szekció vége
ENDSEC	3

Ha különböző színekkel akarunk rajzolni, akkor a POINT, LINE vagy POLYLINE szekcióban is adhatunk meg színeket. A 62-es kód jelenti a színt, utána pedig az adott szín kódja pl az AutoCAD-ben: 1-piros, 2-sárga, 3-zöld, 4-világoskék, 5-sötétkék, 6-lila, 7-fekete/fehér, 8-szürke.

VONAL RAJZOLÁSA

A következő dxf fájl egy vonal a (0.0,0.0) kezdőpontból a (100,200) pontba.

0 Szekció eleje SECTION

2 Rajzi elemek szekció követezik ENTITIES

Vonal típusú elem

LINE

8 Rétegmegadás kódja
vonal 'vonal' a réteg neve
10 X koordináta (kezdőpont)

0.0

20 Y koordináta (kezdőpont)

0.0

11 X koordináta (végpont)

100

Y koordináta (végpont)

200 200 Szekció vége

ENDSEC

O Fájl vége

EGYSZERŰ SZÖVEG ÍRÁSA

írjuk ki a 'Haliho' szöveget a (3,8) pontba, szöveg rétegbe, 1 egység magassággal.

0 SECTION Szekció eleje

Rajzi elemek szekció követezik

0 Szöveg típusú elem

Rétegmegadás kódja

szöveg 'szöveg' a réteg neve

10 3.0 20 8.0 X koordináta 3.0 Y koordináta

8.0 40 Szöveg magassága

1.0 1 rajzi egység 1 Szöveg tartalma: 'Haliho'

0 Szekció vége

0 EOF Fájl vége

Dr Laky Piroska 2016. március 5.

VONALLÁNC RAJZOLÁSA

Vonallánc a (0.0,0.0) kezdőpontból a (34.5,23.2) ponton át a (56.0,16.2) pontba.

0	Szekció eleje
SECTION 2 ENTITIES	Rajzi elemek szekció követezik
0 POLYLINE	Vonallánc típusú elem
8 vonal	Rétegmegadás kódja 'vonal' a réteg neve
66 ¹	Csomópontok következnek
1 0	értéke mindig 1 Csomópont következik
VERTEX 8 ²	Rétegmegadás kódja
vonal 10	'vonal' a réteg neve X koordináta (kezdőpont)
0.0 20	0.0 Y koordináta (kezdőpont)
0.0	0.0 Csomópont következik
VERTEX 8	Rétegmegadás kódja
vonal 10	'vonal' a réteg neve X koordináta (kezdőpont)
34.5 20	34.5 Y koordináta (kezdőpont)
23.2	23.2 Csomópont következik
VERTEX 8	Rétegmegadás kódja
vonal	'vonal' a réteg neve
10 56.0	X koordináta (kezdőpont) 56.0
20 16.2	Y koordináta (kezdőpont) 16.2
0 SEQEND	Csomópontok vége
0 ENDSEC	Szekció vége
0 EOF	Fájl vége

 $^{\rm 1}\,$ A 66-os kód jelöli, hogy csomópontok következnek, ez nem minden CAD programnál kötelező elem, de a tanszéki AutoCAD MAP 2008 változatnál igen.

² Lásd mint előbb. Nem minden CAD programnál kötelező minden csomópontnál megadni a réteg nevét is, de az AutoCAD MAP 2008 esetében igen.

A FENTI RAJZI ELEMEK EGY FÁJLBAN

simple_dxf_example.dxf	8.0 40
0	1.0
SECTION	1
2	Haliho!
HEADER	0
9	POLYLINE
\$PDMODE	8
70	vonal
34	66
0	1
ENDSEC	0
0	VERTEX
SECTION	8
2	vonal
ENTITIES	10
0 POINT	0.0 20
8	0.0
pontok	0.0
10	VERTEX
35.23	8
20	vonal
12.89	10
0	34.5
LINE	20
8	23.2
vonal	0
10	VERTEX
0.0	8
20	vonal
0.0	10
11	56.0
100	20
21 200	16.2 0
0	SEQEND
TEXT	0
8	ENDSEC
szöveg	0
10	EOF
3.0	
20	

1. TÁBLÁZAT ÁLTALÁNOS KÓDOK JELENTÉSE A DXF FÁJLBAN³

0	Text string indicating the entity type (fixed)
1	The primary text value for an entity
2	Name (attribute tag, block name, and so on)
3-4	Other textual or name values
5	Entity handle. Text string of up to 16 hexadecimal digits (fixed)
6	Line type name (fixed)
7	Text style name (fixed)

³ lásd részletesebben: http://www.autodesk.com/techpubs/autocad/acadr14/dxf/index.htm

8	Layer name (fixed)
9	Variable name identifier (used only in HEADER section of the DXF file)
	(Example: \$PDMODE – point style)
10	Primary point. This is the start point of a line or text entity, center of a
	circle, and so on.
	DXF: X value of the primary point (followed by Y and Z value codes 20
	and 30)
11-18	Other X coordinates
20	Primary Y coordinate. 2n values always correspond to 1n values and
	immediately follow them in the file
21-28	Other Y coordinates
30	Primary Z coordinate. 3n values always correspond to 1n and 2n values
	and immediately follow them int he file
31-37	Other Z coordinates
38	DXF: entity's elevation if nonzero.
39	Entity's thickness if nonzero (fixed)
40-48	Floating-point values (text height, scale factors, etc.)
49	Repeated floating-point value. Multiple 49 groups may appear in one entity for
	variable-length tables (such as the dash lengths in the LTYPE table). A $7x$
	group always appears <i>before</i> the first 49 group to specify the table length.
50-58	Angles
62	Color number (fixed)
66	"Entities follow" flag (fixed)
67	Spacethat is, model or paper space (fixed)
68	Identifies whether viewport is on but fully off screen, is not active, or is off
69	Viewport identification number
70-78	Integer values such as repeat counts, flag bits, or modes
210, 220, 230	X, Y, and Z components of extrusion direction (fixed)
999	Comments
etc.	

2. TÁBLÁZAT RAJZI ELEMEK $(\mathsf{ENTITIES}\ \mathsf{SECTION})^4$

20, 30 (point), 50 (angle of X axis for the UCS in effect when the Point was wn -optional 0, for use when PDMODE is nonzero). MODE:34
MODE:34
20, 30 (center), 40 (radius).
20, 30 (center), 40 (radius), 50 (start angle), 51 (end angle).
("vertices follow flag"), 70 (Polyline flags), 40 (default starting width), 41 (default sting width), 71 and 72 (poly- gon mesh M and N vertex counts -optional 0), 73 default surface M and N densities -optional 0), 75 (smooth surface type -ional 0). The default widths apply to any vertex that doesn't supply widths (see low). The "vertices follow" flag is always 1, indicating that a series of VERTEX ities is expected to follow the POLYLINE, terminated by a sequence end EQEND) entity. The "polyline flags" group is a bit-coded field with bits defined as lows: If you will be a sequence of the code of t

 $^{^4 \} l\'{a}sd \ r\'{e}szletesebben: http://www.autodesk.com/techpubs/autocad/acadr 14/dxf/index.htm$

	6 = cubic B-spline surface
	8 = Bezier surface
	32 The polygon mesh is closed in the N direction
VERTEX	10, 20, 30 (location), 40 (starting width -optional, see above), 41 (ending width -optional, see above), 42 (bulge), 70 (vertex flags), 50 (curve fit tangent direction -optional). The bulge is the tangent of 1/4 the included angle for an arc segment, made negative if the arc goes clockwise from the start point to the end point; a bulge of 0 indicates a straight segment, and a bulge of 1 is a semicircle. The meanings of the bit-coded "vertex flags" are shown in the following table. Flag bit value Meaning Extra vertex created by curve fitting Curve fit tangent defined for this vertex. A curve fit tangent direction of 0 may be omitted
	from the DXF output, but is significant if this bit
	is set.
	4 Unused (never set in DXF files)8 Spline vertex created by spline fitting
	16 Spline frame control point
	32 3D Polyline vertex
	64 3D polygon mesh vertex
SEQUEND	No fields. This entity marks the end of vertices (VERTEX type name) for a Polyline,
	or the end of Attribute entities (ATTRIB type name) for an INSERT entity that has
	Attributes (indicated by 66 group present and nonzero in INSERT entity).
TEXT	10, 20, 30 (insertion point), 40 (height), 1 (text value), 50 (rotation angle -optional 0), 41 (relative X scale factor -optional 1), 51 (obliquing angle -optional 0), 7 (text style name -optional "STANDARD"), 71 (text generation flags -optional 0), 72 (justification type -optional 0), 11, 21, 31 (alignment point -optional, appears only if 72 group is resent and nonzero). The "text generation flags" are a bit-coded field with meanings as follows: Flag bit value Meaning Text is backwards (mirrored in X) Text is upside down (mirrored in Y)
	The "justification type" value (not bit-coded) indicates the text justification style used on this entity, as shown in the following table.
	Value Meaning
	Text is left justified Text is centered along its baseline
	2 Text is right justified
	3 Text is aligned between two points (height varies)
	4 Text is "middle" (fully) centered
	5 Text is fit between two points (width varies)
	If the justification is anything other than 0 (left justified), 11, 21, and 31 groups will also appear in the entity to specify the alignment point of the text (center, right-most, or second alignment point).
	DXFOUT handles ASCII control characters in text strings by expanding the character into a "^" (caret) followed by the appropriate letter. For example, an ASCII Control-G (BEL, decimal code 7) is output as "^G". If the text itself contains a caret character, it is expanded to "^ " (caret, space). DXFIN performs the complementary conversion.