AurumOS
Jewellery management system

Multi-PC Setup Guide

Connect your staff computers to the main PC, so every bill reaches one place.

WHAT IS INSIDE

How this works 1
Layout, requirements and seat limits

Part 1 · Set up the main PC 2
The computer that holds the shop

Part 2 · Connect a staff PC 3
Checking the address and joining

Part 3 · Day to day 4
What staff see, and common questions

Part 4 · When something goes wrong 5
Symptoms, causes and fixes

Part 5 · What is finished, and what is not 6
Read this first


PRE-RELEASE · NOT YET SHIPPED

See Part 5 for exactly what is finished and what is not.

Internal draft · Prepared for the AurumOS rollout

How this works

One computer is the **main PC**. It holds the shop and runs a small server the other computers talk to. Every other computer is a **staff PC**. A staff PC keeps its own copy of the data so a brief network drop does not stop a sale, but it cannot let anyone in on its own: passwords are checked on the main PC.



The main PC must be switched on

Staff computers sign in through it. If it is off, or the two machines are on different networks, staff cannot start work. That is deliberate, not a fault.

Before you start

Requirement	Detail
Same network	Every PC on one router, by cable or Wi-Fi. A guest network will not work.
Windows	Windows 10 or 11, with .NET Desktop Runtime 8.0 or later.
Same version	Install the same AurumOS build on every computer.
Licence	Pro or Enterprise. Lite is single-PC only.
Staff accounts	Create them on the main PC first, under Staff.

How many computers you can connect

Plan	Main PC	Staff PCs	Total
Lite	1	None	1
Pro	1	1	2
Enterprise	1	4	5

Need more than four? Extra connections can be added to your plan. They take effect on their own, with no reinstall.

PART 1

Set up the main PC

Do this first, and only on the computer that will hold the shop. This is normally the owner's PC.

1. **Install AurumOS and open it**
   On first run the setup screen appears. Complete Step 1 by entering your licence key and waiting for it to verify.

2. **At Step 2, choose Host Core**
   Step 2 is titled Topology and offers two cards. Pick **Host Core** on the left. This is the card that makes the computer the server.

3. **Fill in your shop details and finish**
   Enter the business name, owner, and the owner password at Step 3. Keep this password private. It is the only account with full access.

4. **Add your staff accounts**
   Sign in, open **Staff**, and create one account per person, each with its own password. Staff sign in on their own PC with these.

5. **Write down this PC's address**
   You need it on every staff computer. Finding it is described below.

> **Windows Firewall will block staff PCs until you allow it**
> This is the single most common reason a staff computer cannot connect. Windows blocks incoming connections by default, so the main PC will look switched off to every other computer. Open Command Prompt as administrator on the main PC and run the command below, once.

```
netsh advfirewall firewall add rule name="AurumOS Shop Server" dir=in action=allow
protocol=TCP localport=58903
```

Finding the address of the main PC

Open Command Prompt on the main PC and run **`ipconfig`**. Look for **IPv4 Address**. It usually starts with 192.168 and looks like 192.168.1.15. That is what staff computers need.

> **Addresses can change on their own**
> Most routers hand out addresses that change after a restart. If staff PCs stop connecting one morning, this is almost always why. Ask whoever manages your router to reserve a fixed address for the main PC and the problem disappears for good.

PART 2

Connect a staff PC

Repeat this on each staff computer. It takes about two minutes per machine.

1. **Install AurumOS and open it**
   The same setup screen appears. Complete Step 1 with the same licence key you used on the main PC.

2. **At Step 2, choose Client Node**
   Pick the **Client Node** card on the right. An address box appears underneath it.

3. **Type the main PC address and press Check**
   Enter the address you wrote down, for example 192.168.1.15, then press **Check**. Do not guess: the next step explains what the answer means.

4. **Confirm the shop name that comes back**
   A green panel shows the name of the shop that answered. If that is your shop, you reached the right computer. If it names a different shop, you typed the address of the wrong machine.

5. **Continue and finish**
   The staff PC joins the shop and appears on the owner's list of connected computers.

6. **Sign in**
   The login screen shows a **Staff terminal** badge with your shop name. The staff member enters their own password, and the computer opens straight into the screen they are allowed to use.

If the check does not go green

What you see	What it means	What to do
No answer from that address	Nothing is listening there.	Check the main PC is on and AurumOS is open. Then check the firewall command in Part 1 was run.
Not running AurumOS	Something answered, but it is another device.	You have the address of the wrong machine. Run ipconfig on the main PC again.
Could not be reached	The two PCs cannot see each other.	Put both on the same router. Guest Wi-Fi separates devices on purpose.
A different shop name	You reached an AurumOS PC, but not yours.	Check each number of the address carefully.
This licence connects N PCs	Every seat is already taken.	Remove a computer you no longer use on the main PC, or add a connection to your plan.

PART 3

Day to day

What a staff member sees

A staff computer shows only what that person has been given. Someone set up for billing opens the billing screen and sees nothing else in the sidebar. They cannot open settings, staff accounts, or year end, and they cannot delete a bill.

Turning a computer on and off

Start the main PC first and leave AurumOS open on it while the shop is trading. Staff computers can be started and shut down freely. At closing time, shut the staff computers down before the main PC so nothing is left mid-sale.

> **A short network drop is not a problem**
>
> If the network flickers, a staff computer holds what it is doing and picks up again by itself once the connection returns. Nobody has to sign in again.

Common questions

Question	Answer
Can staff use the owner password?	They can sign in with it, but the computer still gives them a staff session only. Full access exists on the main PC alone.
Can two people bill at once?	Yes. Each computer numbers its own bills, and the numbers never collide.
What if the main PC breaks?	Staff computers stop after a few minutes. Each holds its own copy of the data, so nothing recorded is lost.
Does this work over the internet?	No. It is designed for computers in one shop on one router.
Can a staff PC print tags?	Yes, on a printer attached to that computer.

PART 4

When something goes wrong

Symptom	Most likely cause	Fix
Every staff PC stopped at once	The main PC is off, asleep, or AurumOS was closed on it.	Wake the main PC and open AurumOS. Set its power settings so it never sleeps during shop hours.
One staff PC stopped, the rest are fine	That computer lost the network.	Check its cable or Wi-Fi. It reconnects on its own once the network returns.
Worked yesterday, not today	The main PC was given a different address by the router.	Run ipconfig on the main PC and set the new address on each staff PC. Reserve a fixed address to stop it recurring.
Staff PC connects but the password fails	The account does not exist, or the password is wrong.	Check under Staff on the main PC. Passwords live there, not on the staff computer.
Cannot connect after five wrong tries	Guessing protection has paused that computer.	Wait five minutes and try again with the correct password.
A new PC will not join	All the seats your plan allows are in use.	Remove an unused computer on the main PC, or add a connection to your plan.

Before calling for help

Note which computers are affected, whether the main PC is on, and the exact wording of the message on screen. Those three things identify almost every case in the table above.

PART 5

What is finished, and what is not

This feature is **not complete**. The joining and sign-in flow in Parts 1 to 3 is built and tested. Three pieces are still outstanding, and one of them affects security. Read this before putting the guide in front of a customer.

Built and tested

Piece	State
Checking the main PC address from setup	Done
Joining a staff PC to the shop	Done
Sign-in answered by the main PC	Done
Seat limits for Pro and Enterprise	Done
Blocking a computer from the main PC	Done, no screen for it yet
Sidebar limited to assigned screens	Done

Still to do

Piece	Why it matters
Enforce permissions inside the application	The sidebar hides what a staff member may not use, but the underlying commands can still be reached by someone determined. Until this lands, treat the staff limits as tidiness, not security.
A screen for assigning staff to a computer	Assigning works underneath, but the owner has no page to do it from, so every staff PC currently gets the plan default.
Remove the old networking code	About 1,400 lines of the previous attempt are still in place and inert. Until they go, the new server runs on a different port to avoid a clash.
Test across two real computers	Everything so far was proved on one machine talking to itself. Real network conditions and Windows Firewall have not been exercised.
Build and distribute a new installer	The changes include a file that cannot be sent out as an update, so every computer needs a fresh install once.

Not ready for a customer site

Because permissions are not yet enforced inside the application, and nothing has run across two real computers, this should stay on test machines until those two items are finished.