
## Case 1 – integration limits are constants:



Patches dS = dxdymust cover whole range  $0 \le x \le 2$  and  $0 \le y \le 1$ .

We essentially do a "partial integration" with respect to x (regarding y as constant) and another with respect to y (x constant).

- amounts to integrating first along a vertical or horizontal strip, then through rest of *S*.

eg: at a given  $y = y_0$ , charge in horizontal strip is  $dy \times \int_{x=0}^{x=2} \sigma(x, y_0) dx = f(y_0) dy.$ 

Then total charge

$$Q = \int_{y=0}^{y=1} f(y) dy = \int_{y=0}^{y=1} \left[ \int_{x=0}^{x=2} \sigma(x, y) dx \right] dy.$$

Taking vertical strips we get the same answer via

$$Q = \int_{x=0}^{x=2} \left[ \int_{y=0}^{y=1} \sigma(x,y) dy \right] dx.$$

### Examples

1.  $\sigma = x^2 + y$ . Perform 2 "partial" integrals, starting with the innermost one:

$$Q = \int_0^2 \left[ \int_0^1 dy (x^2 + y) \right] dx = \int_0^2 \left[ x^2 y + \frac{1}{2} y^2 \right]_0^1 dx$$
$$= \int_0^2 \left( x^2 + \frac{1}{2} \right) dx = \left[ \frac{1}{3} x^3 + \frac{1}{2} x \right]_0^2 = \frac{1}{3} 2^3 + \frac{1}{2} 2 = \frac{11}{3}$$

[Check you get the same if x integral taken 1<sup>st</sup>]


2. 
$$\sigma = x^2 y$$
, so  $Q = \int_{x=0}^{x=2} \left[ \int_{y=0}^{y=1} x^2 y \, dy \right] dx$ .

Safest approach – start from innermost integral.

BUT, as  $\sigma$  can be written as product X(x)Y(y), and limits are constants, can evaluate Q as product of 2 integrals:

$$Q = \int_{x=0}^{x=2} x^2 dx \int_{y=0}^{y=1} y \, dy = \frac{2^3}{3} \frac{1^2}{2} = \frac{4}{3}.$$

# Case 2 – integration limits are NOT constants:



Use equation of lines at boundary to set limits. Choose order of partial integrations to suit.

### **Example:**

$$\sigma = x^2 y$$
;  $S$  area shown, with  $f(x) = 1 - \frac{1}{2}x$ :

Horizontal strips:

$$Q = \int_{y=0}^{y=1} \left[ \int_{x=0}^{x=2(1-y)} x^2 y \, dx \right] dy$$

- must do x integral 1<sup>st</sup>, as it depends on y.

Vertical strips:

$$Q = \int_{x=0}^{x=2} \left[ \int_{y=0}^{y=1-x/2} x^2 y \, dy \right] dx$$

- must do y integral 1<sup>st</sup>, as it depends on x.
- This is easier:

$$Q = \int_{x=0}^{x=2} \left[ \frac{1}{2} x^2 (1 - \frac{x}{2})^2 \right] dx = \dots = \frac{2}{15}.$$

### 3.2.1 Flux & flux integrals

Flux is a measure of the "flow" of some quantity passing through a given area S.

### Examples:

Mass flux - rate of mass flow across unit area


Faraday's Law 
$$\varepsilon = -\frac{\partial \Phi}{\partial t}$$
;  $\Phi$  is "magnetic flux".

Can think of flux as a measure of the number of field (or flux) lines passing through S.

 $\int_{S} \mathbf{F}(\mathbf{r}) \cdot d\mathbf{S}$  and  $\oint_{S} \mathbf{F}(\mathbf{r}) \cdot d\mathbf{S}$  are "flux integrals" of the vector field  $\mathbf{F}(\mathbf{r})$  over surface S. How do they arise?

### Magnetic flux:

Constant magnetic field  $\bf B$ , flat aperture area S:




Define vector  $\mathbf{S} = S\hat{\mathbf{n}}$  with  $\hat{\mathbf{n}}$  normal to aperture.

Then for any 
$$\theta$$
,  $\Phi = \mathbf{B} \cdot \mathbf{S}$  (a scalar)

But what if S is not a simple flat shape, or **B** varies over S (or both)?

Use calculus – split S into small patches  $d\mathbf{S} = dS\hat{\mathbf{n}}$ 



Flux through infinitesimal patch is

$$d\Phi = \mathbf{B}(\mathbf{r}) \cdot d\mathbf{S}$$

Add up all contributions from surface S to find total flux through S for ANY  $\mathbf{B}(\mathbf{r})$  and ANY "open" S:

$$\int_{S} \mathbf{B}(\mathbf{r}) \cdot d\mathbf{S}$$

Note: If S is closed:

- 1. Write  $\oint_S \mathbf{B} \cdot d\mathbf{S}$
- 2. Choose OUTWARD direction for  $d\mathbf{S}$ . Then  $\oint_{S} \mathbf{B} \cdot d\mathbf{S}$  measures net outward flux of  $\mathbf{B}$  across closed surface S.

# 3.2.2 Evaluation of flux integrals


- 1. Split integral into single-face integrals  $\int_{S} \mathbf{F} \cdot d\mathbf{S}$
- 2. For each face
  - (a) Write down  $d\mathbf{S}$  eg  $d\mathbf{S} = -dxdy\mathbf{k}$  (only 2 coordinates will vary;  $d\mathbf{S}$  parallel to 3<sup>rd</sup>)
  - (b) Evaluate dot product  $\mathbf{F} \cdot d\mathbf{S}$
  - (c) Evaluate the (scalar) surface integral
- 3. Add up integrals from each face

Worked example

Evaluate the net flux out of the box  $0 \le x$ , y,  $z \le L$  of the vector field  $\mathbf{F} = 2xyz\mathbf{i} - y^2z\mathbf{j}$ .

Split into 6 integrals, each over 1 of the square faces.

On each face, dS is outward normal



$$I = \oint_{S} \mathbf{F} \cdot d\mathbf{S} = I_{x=0} + I_{x=L} + I_{y=0} + I_{y=L} + I_{z=0} + I_{z=L}$$

On x = 0, L faces,  $d\mathbf{S} = \mp dydz\mathbf{i}$ ,  $\mathbf{F} \cdot d\mathbf{S} = \mp 2xyz\,dydz$ 

On 
$$x = 0$$
 face  $\mathbf{F} \cdot d\mathbf{S} = 0$  so  $I_{x=0} = 0$ .  
On  $x = L$  face  $\mathbf{F} \cdot d\mathbf{S} = +2L \, yz \, dy dz$ , so  $I_{x=L} = 2L \int_0^L y \, dy \int_0^L z \, dz = 2L \cdot \frac{L^2}{2} \cdot \frac{L^2}{2} = \frac{L^5}{2}$ 

On y = 0, L faces,  $d\mathbf{S} = \mp dxdz$ **j**,  $\mathbf{F} \cdot d\mathbf{S} = \pm y^2 z \, dxdz$ 

On 
$$y = 0$$
 face  $\mathbf{F} \cdot d\mathbf{S} = 0$  so  $I_{y=0} = 0$ .

On y = L face  $\mathbf{F} \cdot d\mathbf{S} = -L^2 z \, dx dz$ , so

$$I_{y=L} = -L^2 \int_0^L dx \int_0^L z dz = -L^2 \cdot L \cdot \frac{L^2}{2} = -\frac{L^5}{2}$$

On z = 0, L faces,  $d\mathbf{S} = \mp dxdy\mathbf{k}$ ,  $\mathbf{F} \cdot d\mathbf{S} = 0$ , so

$$I_{z=0} = I_{z=L} = 0.$$

Adding up all contributions we get

$$I = 0 + \frac{L^5}{2} + 0 - \frac{L^5}{2} + 0 + 0 = 0$$

[Not a surprise;  $\nabla \cdot \mathbf{F} = 2yz - 2yz = 0$  everywhere & flux and divergence are closely related.]